

Table and Column Definitions Report

Filename:	H:\tempforests\CIMS_LRDW_TAB_COL.pdf
Run by:	CASEOWNER
Report Date:	November 19, 2010 10:10 AM
Total Pages:	11
Total Tables / Views / Materialized Views:	8

Parameters

Workarea:	GLOBAL SHARED WORKAREA
Container:	CIMS
Table / View / Materialized View:	%
Include Tables?	Y
Include Views?	Y
Include Materialized Views?	Y
Data Structure Diagram:	LRDW
Exclude Prefix:	
Include Table / View / MV Descriptions?	Y
Include Table / View / MV Comments?	N
Include Column Descriptions?	Y
Include Column Comments?	N
Include Column Notes?	Y
Include Unique Constraints?	Y
Include Foreign Key Constraints?	Y
Include Check Constraints?	Y
Include Indexes?	Y

Table: CIMS_HARVEST_RISK_SITE*Description:*

A CIMS HARVEST RISK SITE is the site for a harvest type of Risk Evaluation. The harvest site is a cut block.

Columns:

<u>Seq.</u>	<u>Column</u>	<u>Nulls?</u>	<u>Type</u>
* 10	RISK_SITE_ID A RISK SITE ID is a unique number used to identify a Risk Site.	NOT NULL	NUMBER(10)
20	FOREST_FILE_ID A FOREST FILE ID is a file identification assigned to Provincial Forest Use files. It is an assigned file number. It is usually the Licence, Tenure or Private Mark number.	NULL	VARCHAR2(10)
30	TIMBER_MARK A TIMBER MARK is a unique identifying set of characters to be stamped or marked on the end of each log to associate the log with the specific authority to harvest and move timber.	NULL	VARCHAR2(6)
40	CUTTING_PERMIT_ID A CUTTING PERMIT ID is an identifier for a cutting permit associated with a quota type tenure.	NULL	VARCHAR2(3)
50	CUT_BLOCK_ID A CUT BLOCK ID is an identifier for a cut block of a harvesting tenure (within a cutting permit for tenures with cp's).	NULL	VARCHAR2(10)
60	BLK_FOREST_FILE_ID A FOREST FILE ID is a file identification assigned to Provincial Forest Use files. It is an assigned file number. It is usually the Licence, Tenure or Private Mark number. This forest file id is used to associate the Cutting Permit of a Woodlot Licence or Tree Farm Licence with the Cut Block of a Private Timber Mark or Timber Licence that has the authority to cut granted by the WL or TFL CP.	NULL	VARCHAR2(10)
70	BLK_CUT_PERMIT_ID A CUTTING PERMIT ID is an identifier for a cutting permit associated with a quota type tenure. This cutting permit id is used to associate the Cutting Permit of a Woodlot Licence or Tree Farm Licence with the Cut Block of a Private Timber Mark or Timber Licence that has the authority to cut granted by the WL or TFL CP.	NULL	VARCHAR2(3)
80	ENTRY_TIMESTAMP ENTRY TIMESTAMP is the date and time that the record was initially created.	NOT NULL	DATE
90	ENTRY_USERID An ENTRY USERID is the userid of the user that initially created the record.	NOT NULL	VARCHAR2(30)
100	UPDATE_TIMESTAMP An UPDATE TIMESTAMP is the date and time of the most recent update to the record.	NOT NULL	DATE
110	UPDATE_USERID An UPDATE USERID is the userid of the most recent user to update the record.	NOT NULL	VARCHAR2(30)

Indexes:

CIMS_HARV_RSITE_CUT_BLOCK_FK_I
FOREST_FILE_ID
CUT_BLOCK_ID
TIMBER_MARK
CIMS_HARV_RSITE_RISK_SITE_FK_I
RISK_SITE_ID

Table: CIMS_RISK_ACTIVITY_LIST_MVW**Description:**

A CIMS RISK ACTIVITY LIST MVW is a summary of risk site information for a particular site.

Columns:

<u>Seq.</u>	<u>Column</u>	<u>Nulls?</u>	<u>Type</u>
* 10	RISK_SITE_ID A RISK SITE ID is a unique number used to identify a Risk Site.	NOT NULL	NUMBER(10)
170	INSPECTION_COUNT INSPECTION COUNT is a count of the number of inspections which have been completed for this site, as calculated in the Inspections module of CIMS.	NULL	NUMBER(10)
350	REINSPECTION_DATE A REINSPECTION DATE is the date than an inspector has determined that another inspection on the site should be conducted.	NULL	DATE
360	RIPARIAN RIPARIAN is a risk element that applies to the Harvest, Road and Range riparian areas/fish habitat values. It indicates the number of riparian areas on the site.	NULL	NUMBER(10)
520	CIMS_BUSINESS_AREA_CODE A CIMS BUSINESS AREA CODE is a code identifying the Business Area of interest for CIMS. Values are GEN = General, HARV = Harvest, REC = Recreation, RNGE = Range, ROAD = Road, SILV = Silviculture.	NOT NULL	VARCHAR2(10)
530	RISK_EVALUATION_ID A RISK EVALUATION ID is a unique identifier for a Risk Evaluation.	NULL	NUMBER(10)
540	INSPECTION_SEASON_CODE An INSPECTION SEASON CODE is a code identifying the valid inspection seasons. Values are DRY = Dry, FA = Fall, SP = Spring, SU = Summer, WET = Wet, WI = Winter.	NULL	VARCHAR2(10)
550	EUSER_ID A EUSER ID is a unique number used to identify an EUser.	NULL	NUMBER(10)
560	RISK_EVALUATION_TYPE A RISK EVALUATION TYPE is a code identifying the type of Risk Evaluation. Values are AS = Assessment, ES = Estimate.	NULL	VARCHAR2(10)
570	CATEGORY_ID A CATEGORY ID is a unique identifier for a site category.	NULL	NUMBER(10)
580	INSPECTION_ID An INSPECTION_ID is a unique identifier for an Inspection Report.	NULL	NUMBER(10)
590	SITE_STATUS_CODE A SITE STATUS CODE is a code identifying the current status of the site. Values are ACT = Active, INA = Inactive, COM = Complete.	NOT NULL	VARCHAR2(10)
600	COMPLAINT_SEVERITY_CODE COMPLAINT SEVERITY CODE is a code identifying the severity of a public complaint. Values are H = High, L = Low, N = N/A.	NULL	VARCHAR2(10)
610	INSPECTION_PRIORITY_CODE An INSPECTION PRIORITY CODE is the priority to do an inspection on a site. Examples are: H = High, L = Low, M = Moderate, V = Very High.	NULL	VARCHAR2(10)
620	RISK_SITE_ACCESS_CODE A RISK SITE ACCESS CODE is a code identifying the method of transportation needed to access a site. Examples are AIR = Air, WAT = Water, VEH = Motor Vehicle.	NULL	VARCHAR2(10)

Indexes:

CIMS_RACT_LIST_INSPECTION_FK_I
INSPECTION_ID
CIMS_RACT_LIST_RISK_FK_I
RISK_EVALUATION_ID
CIMS_RACT_LIST_RISK_SITE_FK_I
RISK_SITE_ID
CIMS_RACT_LIST_SSC_FK_I
SITE_STATUS_CODE

Table: CIMS_RISK_EVALUATION*Description:*

A CIMS RISK EVALUATION is the evaluation of risk of an activity for a particular site as determined by Compliance and Enforcement staff. An evaluation is completed as either an Assessment or Estimate. An assessment is conducted using information from site specific plans. Where this site-specific information is not available, a risk estimate is conducted. Individual Site Priorities are later determined, based on the information captured in the Risk evaluation.

Columns:

<u>Seq.</u>	<u>Column</u>	<u>Nulls?</u>	<u>Type</u>
* 10	RISK_EVALUATION_ID A RISK EVALUATION ID is a unique identifier for a Risk Evaluation.	NOT NULL	NUMBER(10)
20	EVALUATION_DATE An EVALUATION DATE is the date that the Risk Evaluation was completed. This date may be different from the date the Risk Evaluation is entered into CIMS.	NOT NULL	DATE
30	LICENSEE_COMPLETED_IND A LICENSEE COMPLETED IND indicates whether the Risk Evaluation was originally completed by the licensee.	NOT NULL	VARCHAR2(1)
40	LICENSEE_VARIANCE_IND A LICENSEE VARIANCE IND indicates whether there is a variance between the licensee's and MoFR staff evaluations.	NOT NULL	VARCHAR2(1)
50	LICENSEE_VARIANCE_COMMENT A LICENSEE VARIANCE COMMENTS are comments entered by MoFR staff to detail the variance between the licensee's and MoFR staff evaluations.	NULL	VARCHAR2(2000)
60	ESTIMATE_COMMENTS ESTIMATE COMMENTS are additional risk factors that were not accounted for in the Risk Estimate. This information is not captured if the Risk Estimate is a member of a Risk Group.	NULL	VARCHAR2(2000)
70	EUSER_ID A EUSER ID is a unique number used to identify an EUser.	NULL	NUMBER(10)
80	RISK_EVALUATION_STATUS_CODE A RISK EVALUATION STATUS CODE is a code identifying the status of the Risk Evaluation. Values are COM = Complete, INC = Incomplete.	NOT NULL	VARCHAR2(10)
90	RISK_EVALUATION_TYPE_CODE A RISK EVALUATION TYPE CODE is a code Identifying the type of Risk Evaluation. Values are AS = Assessment, ES = Estimate.	NOT NULL	VARCHAR2(10)
100	CIMS_BUSINESS_AREA_CODE A CIMS BUSINESS AREA CODE is a code identifying the Business Area of interest for CIMS. Values are GEN = General, HARV = Harvest, REC = Recreation, RNGE = Range, ROAD = Road, SILV = Silviculture.	NOT NULL	VARCHAR2(10)
110	ORG_UNIT_NO An ORG UNIT NO is the geographic district associated with the risk site.	NOT NULL	NUMBER(10)
120	RISK_SITE_ID A RISK SITE ID is a unique number used to identify a Risk Site.	NOT NULL	NUMBER(10)
130	RISK_ESTIMATE_CODE A RISK ESTIMATE CODE is a code identifying the estimated risk level of the activity. Values are H = High, L = Low, M = Moderate, U = Unable to Estimate.	NULL	VARCHAR2(10)
140	RISK_GROUP_ID A RISK GROUP ID is a unique identifier for a Risk Group.	NULL	NUMBER(10)
150	ENTRY_TIMESTAMP ENTRY TIMESTAMP is the date and time that the record was initially created.	NOT NULL	DATE
160	ENTRY_USERID An ENTRY USERID is the userid of the user that initially created the record.	NOT NULL	VARCHAR2(30)
170	UPDATE_TIMESTAMP An UPDATE TIMESTAMP is the date and time of the most recent update to the record.	NOT NULL	DATE
180	UPDATE_USERID An UPDATE USERID is the userid of the most recent user to update the record.	NOT NULL	VARCHAR2(30)

Indexes:

CIMS_RISK_ORG_UNIT_FK_I
ORG_UNIT_NO
CIMS_RISK_RISK_SITE_FK_I
RISK_SITE_ID

Table: CIMS_RISK_SITE*Description:*

A CIMS RISK SITE is the site on which a Risk Evaluation is done. There following are the valid types for a site: Harvest, Road, Silviculture, Recreation, Range, and General.

Columns:

<u>Seq.</u>	<u>Column</u>	<u>Nulls?</u>	<u>Type</u>
* 10	RISK_SITE_ID A RISK SITE ID is a unique number used to identify a Risk Site.	NOT NULL	NUMBER(10)
20	CIMS_BUSINESS_AREA_CODE A CIMS BUSINESS AREA CODE is a code identifying the Business Area of interest for CIMS. Values are GEN = General, HARV = Harvest, REC = Recreation, RNGE = Range, ROAD = Road, SILV = Silviculture.	NOT NULL	VARCHAR2(10)
30	EUSER_ID A EUSER ID is a unique number used to identify an EUser.	NULL	NUMBER(10)
40	SITE_STATUS_CODE A SITE STATUS CODE is a code identifying the current status of the site. Values are ACT = Active, INA = Inactive, COM = Complete.	NOT NULL	VARCHAR2(10)
50	CATEGORY_ID A CATEGORY ID is a unique identifier for a category.	NULL	NUMBER(10)
60	RISK_SITE_ACCESS_CODE A RISK SITE ACCESS CODE is a code identifying the method of transportation needed to access a site. Examples are AIR = Air, WAT = Water, VEH = Motor Vehicle.	NULL	VARCHAR2(10)
70	INSPECTION_SEASON_CODE An INSPECTION SEASON CODE is a code identifying the valid inspection seasons. Values are DRY = Dry, FA = Fall, SP = Spring, SU = Summer, WET = Wet, WI = Winter.	NULL	VARCHAR2(10)
80	COMPLAINT_SEVERITY_CODE COMPLAINT SEVERITY CODE is a code identifying the severity of a public complaint. Values are H = High, L = Low, N = N/A.	NULL	VARCHAR2(10)
90	PROJECTED_ACTIVE_DATE A PROJECTED ACTIVE DATE is the date that activity is projected to start on the site. For a Harvest site this would be the date that harvesting is to start on the site.	NULL	DATE
100	COMMENTS COMMENTS are general comments regarding issues on the site that may impact inspections and risk evaluations.	NULL	VARCHAR2(2000)
110	WEATHER WEATHER is comments regarding any specific weather or weather related data on the site that may impact inspections and risk evaluations.	NULL	VARCHAR2(100)
120	SEASONAL_EVENTS SEASONAL EVENTS are comments regarding any specific seasonal events on the site that may impact inspections and risk evaluations.	NULL	VARCHAR2(100)
130	WILDLIFE_DEMANDS WILDLIFE DEMANDS are comments regarding any specific demands that are put upon the site by wildlife.	NULL	VARCHAR2(100)
140	ENTRY_TIMESTAMP ENTRY TIMESTAMP is the date and time that the record was initially created.	NOT NULL	DATE
150	ENTRY_USERID An ENTRY USERID is the userid of the user that initially created the record.	NOT NULL	VARCHAR2(30)
160	UPDATE_TIMESTAMP An UPDATE TIMESTAMP is the date and time of the most recent update to the record.	NOT NULL	DATE
170	UPDATE_USERID An UPDATE USERID is the userid of the most recent user to update the record.	NOT NULL	VARCHAR2(30)

Indexes:

CIMS_RISK_SITE_SSC_FK_I
SITE_STATUS_CODE

Table: CIMS_ROAD_RISK_SITE*Description:*

A CIMS ROAD RISK SITE is the site for a road type of Risk Evaluation. The road site is a road section.

Columns:

<u>Seq.</u>	<u>Column</u>	<u>Nulls?</u>	<u>Type</u>
* 10	RISK_SITE_ID A RISK SITE ID is a unique number used to identify a Risk Site.	NOT NULL	NUMBER(10)
20	FOREST_FILE_ID A FOREST FILE ID is a file identification assigned to Provincial Forest Use files. It is an assigned file number. It is usually the Licence, Tenure or Private Mark number.	NOT NULL	VARCHAR2(10)
30	ROAD_SECTION_ID A ROAD SECTION ID identifies one section of a road within a road permit.	NOT NULL	VARCHAR2(10)
40	CIMS_ROAD_STATUS_CODE A CIMS ROAD STATUS CODE is a code identifying the status of the activity on a road section. Values are DP = Deactivated (Permanent), DS = Deactivated (Semi-Permanent), DT = Deactivated (Temporary), RC = Construction, RM = Maintenance.	NOT NULL	VARCHAR2(10)
50	ENTRY_TIMESTAMP ENTRY TIMESTAMP is the date and time that the record was initially created.	NOT NULL	DATE
60	ENTRY_USERID An ENTRY USERID is the userid of the user that initially created the record.	NOT NULL	VARCHAR2(30)
70	UPDATE_USERID An UPDATE USERID is the userid of the most recent user to update the record.	NOT NULL	VARCHAR2(30)
80	UPDATE_TIMESTAMP An UPDATE TIMESTAMP is the date and time of the most recent update to the record.	NOT NULL	DATE

Indexes:

CIMS_ROAD_RSITE_ROAD_SECT_FK_I
FOREST_FILE_ID
ROAD_SECTION_ID

Table: CIMS_SILVICULTURE_RISK_SITE*Description:*

A CIMS SILVICULTURE RISK SITE is the site for a silviculture type of Risk Evaluation. The silviculture site is an opening, which is usually associated with a cut block.

Columns:

<u>Seq.</u>	<u>Column</u>	<u>Nulls?</u>	<u>Type</u>
* 10	RISK_SITE_ID	NOT NULL	NUMBER(10)
	A RISK SITE ID is a unique number used to identify a Risk Site.		
20	CUT_BLOCK_OPEN_ADMIN_ID	NOT NULL	NUMBER(10)
	A CUT BLOCK OPEN ADMIN ID is a primary Unique identifier for a Cut Block Open Admin.		
30	ENTRY_TIMESTAMP	NOT NULL	DATE
	ENTRY TIMESTAMP is the date and time that the record was initially created.		
40	UPDATE_TIMESTAMP	NOT NULL	DATE
	An UPDATE TIMESTAMP is the date and time of the most recent update to the record.		
50	ENTRY_USERID	NOT NULL	VARCHAR2(30)
	An ENTRY USERID is the userid of the user that initially created the record.		
60	UPDATE_USERID	NOT NULL	VARCHAR2(30)
	An UPDATE USERID is the userid of the most recent user to update the record.		

Indexes:

CIMS_SILV_RSITE_CBOA_FK_I
CUT_BLOCK_OPEN_ADMIN_ID

Table: CIMS_SITE_PRIORITY*Description:*

A CIMS SITE PRIORITY is the priority to inspect a particular site. Inspectors use the Site Priority to aid them in setting realistic and achievable inspection objectives. The Site Priority is based on the information in the Risk Evaluation.

Columns:

<u>Seq.</u>	<u>Column</u>	<u>Nulls?</u>	<u>Type</u>
* 10	RISK_EVALUATION_ID A RISK EVALUATION ID is a unique identifier for a Risk Evaluation.	NOT NULL	NUMBER(10)
20	INSPECTION_PRIORITY_CODE An INSPECTION PRIORITY CODE is the priority to do an inspection on a site. Examples are: H = High, L = Low, M = Moderate, V = Very High.	NOT NULL	VARCHAR2(10)
30	INITIAL_SITE_PRIORITY An INITIAL SITE PRIORITY is the priority that is calculated from site's risk evaluation (estimate and assessment) and the District Inspection Plan. The calculated priority is based on the attributes of the site and is not impacted by any contributing or mitigating factors. The contributing and mitigating factors are used in determining the INSPECTION PRIORITY CODE.	NOT NULL	VARCHAR2(10)
40	HISTORY_CONTRIBUTING_IND A HISTORY CONTRIBUTING IND indicates if the Compliance History of the obligation holder contributes to the risk on the site or the need for an inspection on the site.	NOT NULL	VARCHAR2(1)
50	CROWN_CONTRIBUTING_IND A CROWN CONTRIBUTING IND indicates if the Potential for the loss of Crown Revenue contributes to the risk on the site or the need for an inspection on the site.	NOT NULL	VARCHAR2(1)
60	SEASON_CONTRIBUTING_IND A SEASON CONTRIBUTING IND Indicates if the Season of operation of weather condicions contribute to the risk on the site or the need for an inspection on the site.	NOT NULL	VARCHAR2(1)
70	PUBLIC_CONTRIBUTING_IND A PUBLIC CONTRIBUTING IND Indicates if Public perception contributes to the risk on the site or the need for an inspection on the site.	NOT NULL	VARCHAR2(1)
80	UNCERTAINTY_CONTRIBUTING_IND An UNCERTAINTY CONTRIBUTING IND indicates if the Uncertainty contributes to the risk on the site or the need for an inspection on the site.	NOT NULL	VARCHAR2(1)
90	OTHER_CONTRIBUTING_IND An OTHER CONTRIBUTING IND indicates if the Other factors contribute to the risk on the site or the need for an inspection on the site.	NOT NULL	VARCHAR2(1)
100	HISTORY_MITIGATING_IND A HISTORY MITIGATING IND indicates if the Compliance History of the obligation holder mitigates the risk on the site or the need for an inspection on the site.	NOT NULL	VARCHAR2(1)
110	SEASON_MITIGATING_IND A SEASON MITIGATING IND indicates if the Season of operation or weather conditions mitigate the risk on the site or the need for an inspection on the site.	NOT NULL	VARCHAR2(1)
120	OTHER_MITIGATING_IND An OTHER MITIGATING IND indicates if Other factors mitgate the risk on the site or the need for an inspection on the site.	NOT NULL	VARCHAR2(1)
130	RISK_FACTOR_COMMENTS RISK FACTOR COMMENTS provide a commentary about the Contributing and Mitigating factors that were selected for the site priority.	NULL	VARCHAR2(2000)
140	INSPECTION_IMPLICATIONS INSPECTION IMPLICATIONS describe the implications for inspections related to the site priority. Implications for inspections may be related to the appropriate timing or method of inspection, or where on the site to focus.	NULL	VARCHAR2(2000)
150	ENTRY_TIMESTAMP ENTRY TIMESTAMP is the date and time that the record was initially created.	NOT NULL	DATE
160	ENTRY_USERID An ENTRY USERID is the userid of the user that initially created the record.	NOT NULL	VARCHAR2(30)
170	UPDATE_TIMESTAMP An UPDATE TIMESTAMP is the date and time of the most recent update to the record.	NOT NULL	DATE
180	UPDATE_USERID An UPDATE USERID is the userid of the most recent user to update the record.	NOT NULL	VARCHAR2(30)

Indexes:

Table: CIMS_SITE_PRIORITY (cont'd)*Indexes:*

CIMS_SITE_PRTY_PRIORITY_FK_I
INSPECTION_PRIORITY_CODE

Table: CIMS_START_UP_NOTIFICATION*Description:*

CIMS START UP NOTIFICATION provides a record of the notification supplied by a licensee prior to commencement of harvesting on either a cut block or a road section. At a minimum the notification must contain a location of the harvesting and the date harvesting will commence. The notification is usually supplied within a couple of weeks of commencement of harvesting.

Ex. Any time harvesting begins on a cut block or road section, the licensee must supply a notification. In cases where the licensee suspends harvesting for a period of time and then resumes harvesting, the licensee must supply another notification when harvesting resumes.

Columns:

<u>Seq.</u>	<u>Column</u>	<u>Nulls?</u>	<u>Type</u>
* 10	START_UP_NOTIFICATION_ID A START UP NOTIFICATION ID is a unique number for identifying each Start up Notification.	NOT NULL	NUMBER
20	FOREST_FILE_ID A FOREST FILE ID is a file identification assigned to Provincial Forest Use files. It is an assigned file number. It is usually the Licence, Tenure or Private Mark number.	NOT NULL	VARCHAR2(10)
30	TIMBER_MARK A TIMBER MARK is a unique identifying set of characters to be stamped or marked on the end of each log to associate the log with the specific authority to harvest and move timber.	NULL	VARCHAR2(6)
40	CUT_BLOCK_ID A CUT BLOCK ID is an identifier for a cut block of a harvesting tenure (within a cutting permit for tenures with cp's).	NULL	VARCHAR2(10)
50	ROAD_SECTION_ID A ROAD SECTION ID identifies one section of a road within a road permit.	NULL	VARCHAR2(10)
60	RISK_SITE_ID A RISK SITE ID is a unique number used to identify a Risk Site.	NULL	NUMBER(10,0)
70	START_UP_DATE A START UP DATE is the date that harvesting will commence on the site. The date is provided by the licensee.	NOT NULL	DATE
80	SITE_LOCATION A SITE LOCATION is a textual description of the location to be harvested.	NULL	VARCHAR2(500)
90	START_UP_COMMENT A START UP COMMENT is an optional comment that is used to provide additional information about the Start Up Notification.	NULL	VARCHAR2(500)
100	LATITUDE LATITUDE is a global designation for the relative distance north or south from the equator. Values should be between 48 and 60 for the province of British Columbia.	NULL	NUMBER(8,6)
110	LONGITUDE LONGITUDE is a global designation for the relative distance east or west from the Greenwich meridian, (measured in degrees and minutes). Values should be between -113 and -140 for the province of British Columbia.	NULL	NUMBER(9,6)
120	ENTRY_TIMESTAMP ENTRY TIMESTAMP is the date and time that the record was initially created.	NOT NULL	DATE
130	ENTRY_USERID An ENTRY USERID is the userid of the user that initially created the record.	NOT NULL	VARCHAR2(30)
140	UPDATE_TIMESTAMP An UPDATE TIMESTAMP is the date and time of the most recent update to the record.	NOT NULL	DATE
150	UPDATE_USERID An UPDATE USERID is the userid of the most recent user to update the record.	NOT NULL	VARCHAR2(30)

Indexes:

CIMS_SUF_CUT_BLOCK_FK_I
 FOREST_FILE_ID
 CUT_BLOCK_ID
 TIMBER_MARK
 CIMS_SUF_RISK_SITE_FK_I
 RISK_SITE_ID
 CIMS_SUF_ROAD_SECT_FK_I
 FOREST_FILE_ID

Table: CIMS_START_UP_NOTIFICATION (cont'd)*Indexes:*

ROAD_SECTION_ID