
HBS Super-Type Entity
HBS Sub/Super-Type Entity
HBS Entity (to be implemented as physical table)
HBS Sub-type entity to be implemented as column
MOF Referenced System Entity
Entities implemented in different subject area
FOREST CLIENT
CLIENT NUMBER
HBS XML PURGE STATUS CODE
CLIENT LOCATION
CLIENT LOCATION CODE
HBS REPORT STATUS CODE
HBS PROCESSING STATUS CODE
HBS XML TRANS STEP CODE
HBS DELIVERY METHOD CODE
HBS TRANSMISSION
TRANSMISSION ID
* FILE NAME
* ENTRY USERID
* ENTRY TIMESTAMP
DOCUMENT DELIVERY TRANSMISSION
* RECIPIENT TYPE
* PS INVOICE COUNT
* PS VOL STATEMENT COUNT
* WS INVOICE COUNT
* WS VOL STATEMENT COUNT
* COMPILED SAMPLE STMT COUNT
* RATIO STATEMENT COUNT
o PDF FILE NAME
o CREATION DATE
o SENT DATE
o EMAIL ADDRESS
DTL SCL DOC TRANSMISSION
* BATCH COUNT
* ACCEPTED IND
* FILE DATETIME
* RECORD COUNT
o TEST FILE IND
o INPUT USERID
o RECD_DIRECTORY
o HBS_XML_PURGE_TIMESTAMP
o UPDATE USERID
o UPDATE TIMESTAMP
HDBS TRANSMISSION
o FAILURE REASON
* FILE DATETIME
* BATCH COUNT
* RECORD COUNT
* HDBS RETURN COUNT
HBS USER
USER ID
* LAST NAME
* FIRST NAME
* MIDDLE INITIAL
* EMAIL
* PHONE
HBS TS VERSION
HBS TS VERSION ID
* SCHEMA VERSION
* TRANS VERSION
MIME TYPE CODE
OUTPUT BATCH STATUS CODE
HBS RETURN TYPE CODE
SCALE SITE
SCALE_SITE_ID_NMBR
HBS FILE
HBS FILE ID
* FILE SENT IND
* FILE TIMESTAMP
o FILE OBJECT
HBS BATCH
BATCH ID
* ENTRY USERID
* ENTRY TIMESTAMP
DTL DOC BATCH
* DTLDOCBAT TYPE
* BATCH CONTROL TOTAL
* READY COUNT
* IN ERROR COUNT
* FROM SCALE DATE
* TO SCALE DATE
* OTHER COUNT
* RETURN COUNT
* ACCEPTED IND
o SUBMITTER BATCH ID
DOCUMENT DELIVERY BATCH ITEM
HBS OUTPUT BATCH
* RETURN COUNT
o SENT DATE TIME
* RECORD COUNT
* SENT IND
o RECONCILED TXN COUNT
SCALE RETURN STATE CODE
DETAIL SCALE DOC TYPE CODE
HBS TRX STATEMENT
STATEMENT NUMBER
* ISSUE DATE
* ENTRY USERID
* ENTRY TIMESTAMP
HBS RATIO STATEMENT
HBS SMRY RETURN TRX STATEMENT
HBS COMPILED SAMPLE STMNT
HBS WS STATEMENT
HBS PS STATEMENT
HBS WS INVOICE
HBS PS INVOICE
HBS WS VOLUME STATEMENT
HBS PS VOLUME STATEMENT
DETAIL SCALE DOCUMENT
DETAIL DOCUMENT NUMBER
* ENTRY USERID
* ENTRY TIMESTAMP
o UPDATE USERID
o UPDATE TIMESTAMP
DTL DOC BATCH DOCUMENT
BATDOC ID
* ACCEPTED IND
o SOFTWARE PRODUCT
o SOFTWARE VERSION
o SOFTWARE REVISION
o INPUT DDN
o INPUT DV
* ENTRY USERID
* ENTRY TIMESTAMP
SCL RTN VERSION STATE CODE
DETAIL SCALE DOCUMENT VERSION
VERSION
* ACTIVE VERSION IND
* ORIGINAL VERSION IND
* VALID SIGNATURE IND
o TIMBER BRAND
o INPUT SCALE SITE
* DTL DOC SEQ
* ENTRY USERID
* ENTRY TIMESTAMP
o UPDATE USERID
o UPDATE TIMESTAMP
DETAIL SCALE DOC VERSION SUBTYPE
DETAIL SCALE DOC VERSION PROCESSABLE
PIECE SCALED LOG TALLY
LOG TALLY
SAMPLE LOG TALLY
SFP TALLY
SCL SITE DEPARTURE LEDGER
SCL SITE ARRIVAL LEDGER
WEIGH SLIP