Table and Column Definitions Report

Filename:	h:\RESULTS_LRDW_TABLE.pdf
Run by:	GDUFF
Report Date:	August 12, 2008 02:52 PM
Total Pages:	99
Total Tables / Views / Materialized Views:	17

Parameters

Workarea:	GLOBAL SHARED WORKAREA
Container:	RESULTS
Table / View / Materialized View:	%
Include Tables?	Y
Include Views?	Y
Include Materialized Views?	Y
Data Structure Diagram:	SMD RESULTS WAREHOUSE
Exclude Prefix:	
Include Table / View / MV Descriptions?	Y
Include Table / View / MV Comments?	N
Include Column Descriptions?	Y
Include Column Comments?	N
Include Column Notes?	Y
Include Unique Constraints?	Y
Include Foreign Key Constraints?	Y
Include Check Constraints?	Y
Include Indexes?	Y

Table: RSLT_ACTIVITY_TREATMENT_POLY

Description:

The spatial representation of opening's Disturbance and silviculture activities reported into RESULTS. Note that silviculture may have planned activities.

Columns:

Seq.	Column	Nulls?	Type
* 1	ACTIVITY_TREATMENT_UNIT_ID	NOT NULL	NUMBER(10,0)
	The ACTIVITY TREATMENT UNIT ID is a system generated value by RESULTS to uniquely identify the disturbance or silviculture activity.		
2	ACTIVITY_LICENSEE_ID	NULL	VARCHAR2(30)
	The ACTIVITY LICENSEE ID is a unique identifier provided by the Licensee or submitter to identify the disturbance or silviculture activity		
3	OPENING_ID	NOT NULL	NUMBER(10,0)
	The OPENING ID is a system generated value by RESULTS to uniquely identify the opening.		
8	MAP_LABEL	NOT NULL	VARCHAR2(14)
	The default label to be used when displaying the feature on a map. Consists of the SILV BASE CODE, SILV TECHNIQUE CODE, DISTURBANCE CODE, and ATU COMPLETION YEAR.		
9	SILV_BASE_CODE	NOT NULL	VARCHAR2(2)
	The SILV BASE CODE identifies primary category of the completed disturbance or silviculture activity (eg. DN - disturbance, SU - survey, PL-planting etc.)		
10	SILV_TECHNIQUE_CODE	NULL	VARCHAR2(2)
	The SILV TECHNIQUE CODE describes the broad category of technique associated with the completed silviculture activity (eg. Site Prep/Burn - Base Code-SP, Technique Code-BU)		
11	SILV_METHOD_CODE	NULL	VARCHAR2(5)
	The SILV METHOD CODE describes the specific machinery or method used for the completed silviculture activity base/technique combination (eg. Site Prep/Burn/Broadcast: Base Code-SP, Technique Code-BU, Method Code -BROAD)		
12	SILV_OBJECTIVE_CODE_1	NULL	VARCHAR2(3)
	The SILV OBJECTIVE CODE 1 describes the objective for performing the completed silviculture activity.		
13	SILV_OBJECTIVE_CODE_2	NULL	VARCHAR2(3)
	The SILV OBJECTIVE 2 describes the objective for performing the completed silviculture activity.		
14	SILV_OBJECTIVE_CODE_3	NULL	VARCHAR2(3)
	The SILV OBJECTIVE 3 describes the objective for performing the completed silviculture activity.		
15	SILV_FUND_SOURCE_CODE	NULL	VARCHAR2(3)
	The SILV FUND SOURCE CODE describes the actual funding source for the completed silviculture activity on the opening.		
18	ATU_START_DATE	NULL	DATE
	The ATU START DATE is the start date for the disturbance activity. The first disturbance start date for the opening is used to start the milestones for silviculture obligation.		
19	ATU_COMPLETION_DATE	NULL	DATE
	The ATU COMPLETION DATE is the disturbance or silviculture completion date for the activity.		
29	ACTUAL_TREATMENT_AREA	NULL	NUMBER(11,1)
	The ACTIVITY TREATMENT AREA is the completed area for the disturbance/silviculture activity.		
57	ACTUAL_TREATMENT_COST	NULL	NUMBER(9,0)
	The ACTIVITY TREATMENT COST is the completed silviculture cost for the silviculture treatment.		
65	ACTUAL_PLANTED_NUMBER	NULL	NUMBER(10,0)
	The ACTUAL PLANTED NUMBER is the total number of trees planted for the completed planting activity. This is the sum of the trees by species reported.		
75	RESULTS_IND	NULL	VARCHAR2(1)
	The RESULTS IND is a system controlled Yes/No indicator to indicate planned or completed activity.		
80	PLAN_SILV_TECHNIQUE_CODE	NULL	VARCHAR2(2)
	The PLAN SILV TECHNIQUE CODE describes the broad category of technique associated with the planned silviculture activity (eg. Site Prep/Burn - Base Code-SP, Technique Code-BU)		
85	PLAN_SILV_METHOD_CODE	NULL	VARCHAR2(5)
	The PLAN SILV METHOD CODE describes the specific machinery or method used for the planned silviculture activity base/technique combination (eg. Site Prep/Burn/Broadcast: Base Code-SP, Technique Code-BU, Method Code -BROAD)		
90	PLAN_SILV_OBJECTIVE_CODE_1	NULL	VARCHAR2(3)
	The PLAN SILV OBJECTIVE CODE 1 describes the objective for performing the planned silviculture		

Table: RSLT_ACTIVITY_TREATMENT_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	activity.		
95	PLAN_SILV_OBJECTIVE_CODE_2	NULL	VARCHAR2(3)
	The PLAN SILV OBJECTIVE CODE 2 describes the objective for performing the planned silviculture activity.		
105	PLAN_SILV_OBJECTIVE_CODE_3	NULL	VARCHAR2(3)
	The PLAN SILV OBJECTIVE CODE 3 describes the objective for performing the planned silviculture activity.		
125	PLAN_SILV_FUND_SRCE_CODE	NULL	VARCHAR2(3)
	The PLAN SILV FUND SRCE CODE describes the planned funding source for the planned silviculture activity on the opening.		
135	PLANNED_DATE	NULL	DATE
	The PLANNED DATE is the planned date for the disturbance or silviculture activity either specify by the user or derived through treatment regime.		
145	PLANNED_TREATMENT_AREA	NULL	NUMBER(11,1)
	The PLANNED TREATMENT AREA is the planned amount (based on reported unit of measure) for the disturbance/silviculture activity. Majority of activity reporting will be in hectares.		
155	PLANNED_TREATMENT_COST	NULL	NUMBER(9,0)
	The PLANNED TREATMENT COST is the planned estimated silviculture cost for the silviculture treatment.		
185	SILVICULTURE_PROJECT_ID	NULL	VARCHAR2(13)
	The SILVICULTURE PROJECT ID is a RESULTS system-generated unique identifier is assigned to an activity which identified a unit within a RESULTS's project. *TPM 2008-08-06 Updated the column type to be VARCHAR2(13).*		
195	FIA_PROJECT_ID	NULL	VARCHAR2(10)
	The FIA PROJECT ID is a unique identifier provided by user that links to other agencies' databases "Inter-agency Number".		
200	DISTURBANCE_CODE	NULL	VARCHAR2(3)
	The DISTURBANCE CODE is the disturbance origin for the disturbance activity. Some of the Disturbance Code include: L-Logged, B-Burned, S-Salvage, W-Windrow, etc.		
215	SILV_SYSTEM_CODE	NULL	VARCHAR2(5)
	The SILV SYSTEM CODE describes the silvicultural systems used for the harvesting activity. Eg. CLEAR-Clearcut, CCRES-Clearcut with reserves, SELEC-Selection, SHELT-Shelterwood, etc.		
225	SILV_SYSTEM_VARIANT_CODE	NULL	VARCHAR2(3)
	The SILV VARIANT CODE describes the silvcultural system's distribution or removal pattern of the silvicultural system. Eg. GRP-Group; IRR-Irregular; SIN-Single, etc.		
265	SILV_CUT_PHASE_CODE	NULL	VARCHAR2(5)
	The SILV CUT PHASE CODE is the code for the actual silvicultural system cut phase. The cut phase of a silvicultural system variant describes the function of a harvest to extract merchantable timber and achieve regeneration.		
275	CUT_BLOCK_OPEN_ADMIN_ID	NULL	NUMBER(10,0)
	The CUT BLOCK OPEN ADMIN ID is a RESULTS system-generated unique identifier that associates the tenure (licence, cutting permit, timbermark, cutblock) that is reported for disturbance activity.		
285	DISTURBANCE_COMPLETED_IND	NULL	VARCHAR2(1)
	The DISTURBANCE COMPLETED IND is a Yes/No indicator set by the licensee/submitter for the disturbance to identify harvesting is complete on the cutblock. When the indicator is set to "Yes", the cutblock status changes to LC-Logging Complete.		
945	GEOMETRY_EXIST_IND	NULL	VARCHAR2(1)
	The GEOMETRY EXIST IND indicates if there is geometry for the opening. A value of 'Y' indicates there is geometry. A value of 'N' indicates there is no geometry.		
955	GEOMETRY	NULL	
	The GEOMETRY is the Activity Treatment Unit geographical representation.		
965	FEATURE_AREA	NULL	NUMBER(11,4)
	The FEATURE AREA is the area of the feature in square meters.		
975	FEATURE_PERIMETER	NULL	NUMBER(11,4)
	The FEATURE PERIMETER is the perimeter of the feature in meters.		
985	CAPTURE_METHOD_CODE	NULL	VARCHAR2(30)
	The CAPTURE METHOD CODE is a code defining the capture method. (e.g. digitize).		
995	DATA_SOURCE_CODE	NULL	VARCHAR2(10)

Table: RSLT_ACTIVITY_TREATMENT_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	The DATA SOURCE CODE is a code defining the source of the spatial feature (e.g. GPS, TRIM).		
1005	FEATURE_CLASS_SKEY	NULL	NUMBER(10,0)
	The FEATURE CLASS SKEY is the unique key assigned to a Feature Class by the Ministry of Forests.		
1015	OBSERVATION_DATE	NULL	DATE
	The OBSERVATION DATE is the geometry collection date.		
1025	DATA_QUALITY_COMMENT	NULL	VARCHAR2(255)
	The DATA QUALITY COMMENT is a comment indicating the Geometry accuracy.		
1035	ATU_WHO_CREATED	NOT NULL	VARCHAR2(30)
	The ATU WHO CREATED is the USERID of the individual who created the activity record.		
1045	ATU_WHEN_CREATED	NOT NULL	DATE
	The ATU WHO UPDATED is the date and time when the activity record was created.		
1065	ATU_WHO_UPDATED	NOT NULL	VARCHAR2(30)
	The ATU WHEN UPDATED is the USERID of the individual who last updated the activity record.		
1075	ATU_WHEN_UPDATED	NOT NULL	DATE
	THE ATU WHEN UPDATED is the date and time when the activity record was last updated.		
1085	OBJECTID	NOT NULL	INTEGER
	The OBJECTID is a system generated value uniquely identifying the opening. Used by SDE.		
1095	CHANGE_TIMESTAMP1	NOT NULL	DATE
	The date and time of the last update to the ACTIVITY TREATMENT UNIT table.		
4326	CHANGE_TIMESTAMP2	NULL	DATE
	The date and time of the last update to the ACTIVITY TREATMENT GEOMETRY table.		

Unique Constraints:

RSLT_AU_UK
- OBJECTID

Foreign Keys:

RSLT_AU_RSLT_OPEN_FK
- OPENING_ID = RSLT_OPENING_POLYGON.OPENING_ID

Indexes:

RSLT_AU_GEOM_I
- GEOMETRY

RSLT_AU_RSLT_OPEN_FK_I
- OPENING_ID

Table: RSLT_ACTIVITY_TREATMENT_SVW

Description:

The spatial representation of opening's Disturbance and silviculture activities reported into RESULTS. Note that silviculture may have planned activities.

Columns:

Seq.	Column	Nulls?	Type
10	ACTIVITY_TREATMENT_UNIT_ID	NOT NULL	NUMBER(10,0)
	The ACTIVITY TREATMENT UNIT ID is a system generated value by RESULTS to uniquely identify the disturbance or silviculture activity.		
20	ACTIVITY_LICENSEE_ID	NULL	VARCHAR2(30)
	The ACTIVITY LICENSEE ID is a unique identifier provided by the Licensee or submitter to identify the disturbance or silviculture activity		
30	OPENING_ID	NOT NULL	NUMBER(10,0)
	The OPENING ID is a system generated value by RESULTS to uniquely identify the opening.		
31	MAP_LABEL	NOT NULL	VARCHAR2(14)
	The default label to be used when displaying the feature on a map. Consists of the SILV BASE CODE, SILV TECHNIQUE CODE, DISTURBANCE CODE, and ATU COMPLETION YEAR.		
40	SILV_BASE_CODE	NOT NULL	VARCHAR2(2)
	The SILV BASE CODE identifies primary category of the completed disturbance or silviculture activity (eg. DN - disturbance, SU - survey, PL-planting etc.)		
50	SILV_TECHNIQUE_CODE	NULL	VARCHAR2(2)
	The SILV TECHNIQUE CODE describes the broad category of technique associated with the completed silviculture activity (eg. Site Prep/Burn - Base Code-SP, Technique Code-BU)		
60	SILV_METHOD_CODE	NULL	VARCHAR2(5)
	The SILV METHOD CODE describes the specific machinery or method used for the completed silviculture activity base/technique combination (eg. Site Prep/Burn/Broadcast: Base Code-SP, Technique Code-BU, Method Code -BROAD)		
70	SILV_OBJECTIVE_CODE_1	NULL	VARCHAR2(3)
	The SILV OBJECTIVE CODE 1 describes the objective for performing the completed silviculture activity.		
80	SILV_OBJECTIVE_CODE_2	NULL	VARCHAR2(3)
	The SILV OBJECTIVE 2 describes the objective for performing the completed silviculture activity.		
90	SILV_OBJECTIVE_CODE_3	NULL	VARCHAR2(3)
	The SILV OBJECTIVE 3 describes the objective for performing the completed silviculture activity.		
100	SILV_FUND_SOURCE_CODE	NULL	VARCHAR2(3)
	The SILV FUND SOURCE CODE describes the actual funding source for the completed silviculture activity on the opening.		
105	ATU_START_DATE	NULL	DATE
	The ATU START DATE is the start date for the disturbance activity. The first disturbance start date for the opening is used to start the milestones for silviculture obligation.		
110	ATU_COMPLETION_DATE	NULL	DATE
	The ATU COMPLETION DATE is the disturbance or silviculture completion date for the activity.		
120	ACTUAL_TREATMENT_AREA	NULL	NUMBER(11,1)
	The ACTIVITY TREATMENT AREA is the completed area for the disturbance/silviculture activity.		
130	ACTUAL_TREATMENT_COST	NULL	NUMBER(9,0)
	The ACTIVITY TREATMENT COST is the completed silviculture cost for the silviculture treatment.		
140	ACTUAL_PLANTED_NUMBER	NULL	NUMBER(10,0)
	The ACTUAL PLANTED NUMBER is the total number of trees planted for the completed planting activity. This is the sum of the trees by species reported.		
150	RESULTS_IND	NULL	VARCHAR2(1)
	The RESULTS IND is a system controlled Yes/No indicator to indicate planned or completed activity.		
160	PLAN_SILV_TECHNIQUE_CODE	NULL	VARCHAR2(2)
	The PLAN SILV TECHNIQUE CODE describes the broad category of technique associated with the planned silviculture activity (eg. Site Prep/Burn - Base Code-SP, Technique Code-BU)		
170	PLAN_SILV_METHOD_CODE	NULL	VARCHAR2(5)
	The PLAN SILV METHOD CODE describes the specific machinery or method used for the planned silviculture activity base/technique combination (eg. Site Prep/Burn/Broadcast: Base Code-SP, Technique Code-BU, Method Code -BROAD)		
180	PLAN_SILV_OBJECTIVE_CODE_1	NULL	VARCHAR2(3)
	The PLAN SILV OBJECTIVE CODE 1 describes the objective for performing the planned silviculture		

Table: RSLT_ACTIVITY_TREATMENT_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	activity.		
190	PLAN_SILV_OBJECTIVE_CODE_2	NULL	VARCHAR2(3)
	The PLAN SILV OBJECTIVE CODE 2 describes the objective for performing the planned silviculture activity.		
200	PLAN_SILV_OBJECTIVE_CODE_3	NULL	VARCHAR2(3)
	The PLAN SILV OBJECTIVE CODE 3 describes the objective for performing the planned silviculture activity.		
210	PLAN_SILV_FUND_SRCE_CODE	NULL	VARCHAR2(3)
	The PLAN SILV FUND SRCE CODE describes the planned funding source for the planned silviculture activity on the opening.		
220	PLANNED_DATE	NULL	DATE
	The PLANNED DATE is the planned date for the disturbance or silviculture activity either specify by the user or derived through treatment regime.		
230	PLANNED_TREATMENT_AREA	NULL	NUMBER(11,1)
	The PLANNED TREATMENT AREA is the planned amount (based on reported unit of measure) for the disturbance/silviculture activity. Majority of activity reporting will be in hectares.		
240	PLANNED_TREATMENT_COST	NULL	NUMBER(9,0)
	The PLANNED TREATMENT COST is the planned estimated silviculture cost for the silviculture treatment.		
250	SILVICULTURE_PROJECT_ID	NULL	NUMBER(10,0)
	The SILVICULTURE PROJECT ID is a RESULTS system-generated unique identifier is assigned to an activity which identified a unit within a RESULTS's project.		
260	FIA_PROJECT_ID	NULL	VARCHAR2(10)
	The FIA PROJECT ID is a unique identifier provided by user that links to other agencies' databases "Inter-agency Number".		
270	DISTURBANCE_CODE	NULL	VARCHAR2(3)
	The DISTURBANCE CODE is the disturbance origin for the disturbance activity. Some of the Disturbance Code include: L-Logged, B-Burned, S-Salvage, W-Windrow, etc.		
290	SILV_SYSTEM_CODE	NULL	VARCHAR2(5)
	The SILV SYSTEM CODE describes the silvicultural systems used for the harvesting activity. Eg. CLEAR-Clearcut, CCRES-Clearcut with reserves, SELEC-Selection, SHELT-Shelterwood, etc.		
300	SILV_SYSTEM_VARIANT_CODE	NULL	VARCHAR2(3)
	The SILV VARIANT CODE describes the silvcultural system's distribution or removal pattern of the silvicultural system. Eg. GRP-Group; IRR-Irregular; SIN-Single, etc.		
310	SILV_CUT_PHASE_CODE	NULL	VARCHAR2(5)
	The SILV CUT PHASE CODE is the code for the actual silvicultural system cut phase. The cut phase of a silvicultural system variant describes the function of a harvest to extract merchantable timber and achieve regeneration.		
320	CUT_BLOCK_OPEN_ADMIN_ID	NULL	NUMBER(10,0)
	The CUT BLOCK OPEN ADMIN ID is a RESULTS system-generated unique identifier that associates the tenure (licence, cutting permit, timbermark, cutblock) that is reported for disturbance activity.		
330	DISTURBANCE_COMPLETED_IND	NULL	VARCHAR2(1)
	The DISTURBANCE COMPLETED IND is a Yes/No indicator set by the licensee/submitter for the disturbance to identify harvesting is complete on the cutblock. When the indicator is set to "Yes", the cutblock status changes to LC-Logging Complete.		
340	GEOMETRY_EXIST_IND	NULL	VARCHAR2(1)
	The GEOMETRY EXIST IND indicates if there is geometry for the opening. A value of 'Y' indicates there is geometry. A value of 'N' indicates there is no geometry.		
345	GEOMETRY	NULL	
	The GEOMETRY is the Activity Treatment Unit geographical representation.		
350	FEATURE_AREA	NULL	NUMBER(11,4)
	The FEATURE AREA is the area of the feature in square meters.		
360	FEATURE_PERIMETER	NULL	NUMBER(11,4)
	The FEATURE PERIMETER is the perimeter of the feature in meters.		
370	CAPTURE_METHOD_CODE	NULL	VARCHAR2(30)
	The CAPTURE METHOD CODE is a code defining the capture method. (e.g. digitize).		
380	DATA_SOURCE_CODE	NULL	VARCHAR2(10)
	The DATA SOURCE CODE is a code defining the source of the spatial feature (e.g. GPS, TRIM).		

Table: RSLT_ACTIVITY_TREATMENT_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
390	FEATURE_CLASS_SKEY	NULL	NUMBER(10,0)
	The FEATURE CLASS SKEY is the unique key assigned to a Feature Class by the Ministry of Forests.		
400	OBSERVATION_DATE	NULL	DATE
	The OBSERVATION DATE is the geometry collection date.		
410	DATA_QUALITY_COMMENT	NULL	VARCHAR2(255)
	The DATA QUALITY COMMENT is a comment indicating the Geometry accuracy.		
420	ATU_WHO_CREATED	NOT NULL	VARCHAR2(30)
	The ATU WHO CREATED is the USERID of the individual who created the activity record.		
430	ATU_WHEN_CREATED	NOT NULL	DATE
	The ATU WHO UPDATED is the date and time when the activity record was created.		
440	ATU_WHO_UPDATED	NOT NULL	VARCHAR2(30)
	The ATU WHEN UPDATED is the USERID of the individual who last updated the activity record.		
450	ATU_WHEN_UPDATED	NOT NULL	DATE
	THE ATU WHEN UPDATED is the date and time when the activity record was last updated.		
460	OBJECTID	NOT NULL	NUMBER(10,0)
	The OBJECTID is a system generated value uniquely identifying the opening. Used by SDE.		

Table: RSLT_FOREST_COVER_INV_POLY

Description:

Spatial representation of the opening's forest cover attributes. The attributes have been denormalized and are limited to the Inventory attribution of the Forest Cover Polygon.

Columns:

Seq.	Column	Nulls?	Type
* 10	FOREST_COVER_ID	NOT NULL	NUMBER(10,0)
	The FOREST COVER ID is a system-generated value by RESULTS to uniquely identify forest cover polygon.		
20	STOCKING_STANDARD_UNIT_ID	NULL	NUMBER(10,0)
	The STOCKING STANDARD UNIT ID is a system-generated value by RESULTS to uniquely identify standards units.		
30	OPENING_ID	NOT NULL	NUMBER(10,0)
	The OPENING ID is a system generated value by RESULTS to uniquely identify the opening.		
40	STANDARDS_UNIT_ID	NULL	VARCHAR2(4)
	The STANDARDS UNIT ID is an assigned unique identifier that respresents the standards units. The SU that forest cover polygon is assocated with.		
50	SILV_POLYGON_NUMBER	NOT NULL	VARCHAR2(30)
	The SILV POLYGON NUMBER is an assigned unique identifer that represents the forest cover polygon.		
60	SILV_POLYGON_AREA	NOT NULL	NUMBER(7,1)
	The SILV POLYGON AREA is the total area in hectares occupied by each polygon. The sum of all areas for a polygon(s) should not be greater than the opening gross area.		
70	SILV_POLYGON_NET_AREA	NOT NULL	NUMBER(7,1)
	The SILV POLYGON NET AREA is the number of hectares occupied by each polygon. The silviculture polygon net area is the silviculture polygon area minus the sum of all the associated non-mappable areas reported within the forest cover polygon.		
80	SILV_NON_MAPPED_AREA	NULL	NUMBER(7,1)
	The SILV NON MAPPED AREA represents the sum of the total non-mappable area (in hectares) reported within each forest cover polygon.		
90	STOCKING_STATUS_CODE	NULL	VARCHAR2(3)
	The STOCKING STATUS CODE is an indication of growing space occupancy relative to establish standard. Status refers to whether the site has met those standards. Stocking status is most often described as NSR-not satisfactorily restocked, IMM-immature, MAT-mature.		
100	STOCKING_TYPE_CODE	NULL	VARCHAR2(3)
	The STOCKING TYPE CODE is a further classification of stocking status for the polygon. Eg. NAT-natural, PL-planting, etc.		
110	STOCKING_CLASS_CODE	NULL	VARCHAR2(1)
	The STOCKING CLASS CODE represents a numeric code representing a range of stems per hectares. Examples: stocking class 0 is immature; stocking class 1 is mature with 76+ stems/ha > 27.5dbh.		
120	SILV_RESERVE_CODE	NULL	VARCHAR2(1)
	The SILV RESERVE CODE identifies the spatial pattern of a reserve of retention area associated with a silvicultural system. Reserves are forest patches or individual trees retained during harvesting, or other forestry opereations to provide habitat, scenic, biodiversity, and other values. Examples R-Riparian Reserve; W-Wildlife Tree Patch Reserve; etc.		
130	SILV_RESERVE_OBJECTIVE_CODE	NULL	VARCHAR2(3)
	The SILV RESERVE OBJECTIVE CODE refers to the managmenet goal of the reserve. Examples: WTR-Wildlife Tree Retention; RMA-Riparian reserve, etc.		
140	TREE_COVER_PATTERN_CODE	NULL	VARCHAR2(1)
	The TREE COVER PATTERN CODE is the spatial arrangement of residual patches of overstorey (Layer 1). Applies to polygons in which trees are retained as apart of the silvicultural system or disturbance characteristic (eg. stands with overstorey). Examples: 9-Continuous occurrence with very few inclusions.; 8-Continuous occurrence with several inclusions.; etc.		
150	REENTRY_YEAR	NULL	NUMBER(4,0)
	The RE-ENTRY YEAR is the year the next harvest entry is expected to occur in the opening. Applies to partial-cut silvicultural systems.		
160	REFERENCE_YEAR	NOT NULL	NUMBER(4,0)
	The REFERENCE YEAR is the year the forest cover polygon data were collected.		
170	SITE_INDEX	NULL	NUMBER(5,0)
	The SITE INDEX is a measure of forest land productivity. Enter the projected average height in metres of		

Table: RSLT_FOREST_COVER_INV_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	the leading species of the forest cover inventory at 50 years after the stands achieves breast height (1.3m).		
180	SITE_INDEX_SOURCE_CODE	NULL	VARCHAR2(1)
	The SITE INDEX SOURCE CODE is a source or origin of the site index. Example: C-site index from site index curve.		
190	BGC_ZONE_CODE	NULL	VARCHAR2(4)
	The BGC_ZONE_CODE of the Standards Unit, according to the Biogeocmlimatic Ecosystem Classification (BEC) system. Eg. IDF; MS; CWH.		
200	BGC_SUBZONE_CODE	NULL	VARCHAR2(3)
	The BGC SUBZONE CODE of the Standards Unit, according to the BEC system. Eg. dk; xc; mk.		
210	BGC_VARIANT	NULL	VARCHAR2(1)
	The BGC VARIANT according to the BEC system. Eg. 1, 2. A division of the BGC Subzone on the basis of differences in floristic composition of the zonal ecosystem, but usually on the basis of differences in the cover and vigour of the plant species.		
220	BGC_PHASE	NULL	VARCHAR2(1)
	The BGC PHASE, according to the BEC system. Accomodates the variation, resulting from local relief, in the regional climate of the subzones and variants.		
230	BEC_SITE_SERIES	NULL	VARCHAR2(4)
	The Site series for the given biogeoclimatic unit, according to the BEC system. Eg. 01, 04, 05. Site series is the consideration of all ecosystems capable of producing vegetation belonging to the same plant association at climax.		
240	BEC_SITE_TYPE	NULL	VARCHAR2(3)
	The BEC SITE TYPE for certain site series, according to the BEC system. Site type is the partitionment of the site series according to one or more critical site factors thought to affect ecosystem response to management treatments. Eg. MS, NP.		
250	BEC_SERAL	NULL	VARCHAR2(4)
	The BEC SERAL (often termed successional) classification in BEC is an integration of site and vegetation classifications with structural stage development. Eg. Accp, Acho.		
260	FOREST_COVER_INV_TYPE	NULL	VARCHAR2(7)
	The FOREST COVER INV TYPE describes the forest cover stand type characteristics: EVEN, UNEVEN, NONE and UNKOWN.		
270	I_FOREST_COVER_LAYER_ID	NULL	NUMBER(10,0)
	The FOREST COVER LAYER ID is a RESULTS system-generated unique identifer for the layer information.		
280	I_TOTAL_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I TOTAL STEMS PER HA is the total stems per hectare for the "even-aged" forest cover polygon.		
290	I_TOTAL_WELL_SPACED_STEMS_HA	NULL	NUMBER(10,0)
	The I TOTAL WELL SPACED STEMS HA is the total number of well-spaced stems per hectare for the "even-aged" forest cover polygon. Stems density for silviculture layer disregarding the M-value.		
300	I_WELL_SPACED_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I WELL SPACED STEMS PER HA is the number of well-spaced stems per hectare for "even-aged" forest cover polygon. Trees are healthy, preferred or acceptable species and well -spaced using the minimum inter-tree distance in the stocking standards (as deifned by the SU Identifier).		
310	I_FREE_GROWING_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I FREE GROWING STEMS PER HA is the number of free-growing stems per hectare for "even-aged" forest cover polygon. Free growing stem density for the silviculture (based on the M-value). Free growing trees are healthy, preferred, or acceptable species, well-spaced, free from inhibiting brush, and meet or exceed the minimum height (if applicable).		
320	I_CROWN_CLOSURE_PERCENT	NULL	NUMBER(3,0)
	The I CROWN CLOSURE PERCENT represents the closing together of the crowns of trees in a forest as they age and grow effectively blocking sunlight from reaching the forest floor for "even-aged" forest cover polygon.		
330	I_BASAL_AREA	NULL	NUMBER(5,0)
	The I BASAL AREA is the cumulative cross-sectional residual basal area (in hectares) of all stems >12.5cm dbh for "even-aged" forest cover polygon. Required if basal area is a part of stocking standard.		
350	I_SPECIES_CODE_1	NULL	VARCHAR2(8)
	The I SPECIES CODE 1 represents the tree species (primary, secondary, tertiary, etc.) with the forest		

Table: RSLT_FOREST_COVER_INV_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	cover polygon for the inventory "even-aged" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
360	I_SPECIES_PERCENT_1	NULL	NUMBER(3,0)
	The I SPECIES PERCENT 1 is the estimate of given inventory "even-aged" component tree species percentage within the forest cover polygon.		
370	I_SPECIES_AGE_1	NULL	NUMBER(5,0)
	The I SPECIES AGE 1 is the average age of the given inventory "even-aged" component tree species percent within the forest cover polygon		
380	I_SPECIES_HEIGHT_1	NULL	NUMBER(3,1)
	The I SPECIES HEIGHT 1 is the average height of the given inventory "even-aged" component leading tree species in metres.		
390	I_SPECIES_CODE_2	NULL	VARCHAR2(8)
	The I SPECIES CODE 2 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "even-aged" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
400	I_SPECIES_PERCENT_2	NULL	NUMBER(3,0)
	The I SPECIES PERCENT 2 is the estimate of given inventory "even-aged" component tree species percentage within the forest cover polygon.		
410	I_SPECIES_AGE_2	NULL	NUMBER(5,0)
	The I SPECIES AGE 2 is the average age of the given inventory "even-aged" component tree species percent within the forest cover polygon		
420	I_SPECIES_HEIGHT_2	NULL	NUMBER(3,1)
	The I SPECIES HEIGHT 2 is the average height of the given inventory "even-aged" component leading tree species in metres.		
430	I_SPECIES_CODE_3	NULL	VARCHAR2(8)
	The I SPECIES CODE 3 is the Tree Species Code representing the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "even-aged" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
440	I_SPECIES_PERCENT_3	NULL	NUMBER(3,0)
	The I SPECIES PERCENT 3 is the estimate of given inventory "even-aged" component tree species percentage within the forest cover polygon.		
450	I_SPECIES_CODE_4	NULL	VARCHAR2(8)
	The I SPECIES CODE 4 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "even-aged" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
460	I_SPECIES_PERCENT_4	NULL	NUMBER(3,0)
	The I SPECIES PERCENT 4 is the estimate of given inventory "even-aged" component tree species percentage within the forest cover polygon.		
470	I_SPECIES_CODE_5	NULL	VARCHAR2(8)
	The I SPECIES CODE 5 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "even-aged" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
480	I_SPECIES_PERCENT_5	NULL	NUMBER(3,0)
	The I SPECIES PERCENT 5 is the estimate of given inventory "even-aged" component tree species percentage within the forest cover polygon.		
490	I_MORE_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	The I MORE SPECIES EXIST IND is 'Y' when this layer contains more than 5 species records; these records are available in RSLT_FOREST_COVER_SPECIES		
500	I_INV_LABEL	NULL	VARCHAR2(160)
	The I INV LABEL is the Inventory Label for "even-aged" forest cover polygon		
510	I1_FOREST_COVER_LAYER_ID	NULL	NUMBER(10,0)
	The I1 FOREST COVER LAYER ID is a RESULTS system-generated unique identifer for the layer information.		
520	I1_TOTAL_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I1 TOTAL STEMS PER HA is the stems per hectare for the "uneven-aged Layer 1-Mature" forest cover polygon.		
530	I1_TOTAL_WELL_SPACED_STEMS_HA	NULL	NUMBER(10,0)

Table: RSLT_FOREST_COVER_INV_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	The I1 TOTAL WELL SPACED STEMS HA is the Total number of well-spaced stems per hectare for the "uneven-aged Layer 1-Mature" forest cover polygon. Stems density for silviculture layer disregarding the M-value.		
540	I1_WELL_SPACED_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I1 WELL SPACED STEMS PER HA is the number of well-spaced stems per hectare for "uneven-aged Layer 1-Mature" forest cover polygon. Trees are healthy, preferred or acceptable species and well -spaced using the minimum inter-tree distance in the stocking standards (as deifned by the SU Identifier).		
550	I1_FREE_GROWING_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I1 FREE GROWING STEMS PER HA is the number of free-growing stems per hectare for "uneven-aged Layer 1-Mature" forest cover polygon. Free gorwing stem density for the silviculture (based on the M-value). Free growing trees are healthy, preferred, or acceptable species, well-spaced, free from inhibiting brush, and meet or exceed the minimum height (if applicable).		
560	I1_CROWN_CLOSURE_PERCENT	NULL	NUMBER(3,0)
	The I1 CROWN CLOSURE PERCENT represents the closing together of the crowns of trees in a forest as they age and grow effectively blocking sunlight from reaching the forest floor for "uneven-aged Layer 1-Mature" forest cover polygon.		
570	I1_BASAL_AREA	NULL	NUMBER(5,0)
	The I1 BASAL AREA is the cumulative cross-sectional residual basal area (in hectares) of all stems >12.5cm dbh for "uneven-aged Layer 1-Mature" forest cover polygon. Required if basal area is a part of stocking standard.		
590	I1_SPECIES_CODE_1	NULL	VARCHAR2(8)
	The I1 SPECIES CODE 1 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 1-Mature" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
600	I1_SPECIES_PERCENT_1	NULL	NUMBER(3,0)
	The I1 SPECIES PERCENT 1 is the estimate of given inventory "uneven-aged Layer 1-Mature" component tree species percentage within the forest cover polygon.		
610	I1_SPECIES_AGE_1	NULL	NUMBER(5,0)
	The I1 SPECIES AGE 1 is the average age of the given inventory "uneven-aged Layer 1-Mature" component tree species percent within the forest cover polygon		
620	I1_SPECIES_HEIGHT_1	NULL	NUMBER(3,1)
	The I1 SPECIES HEIGHT 1 is the average height of the given inventory "uneven-aged Layer 1-Mature" component leading tree species in metres.		
630	I1_SPECIES_CODE_2	NULL	VARCHAR2(8)
	The I1 SPECIES CODE 2 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 1-Mature" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
640	I1_SPECIES_PERCENT_2	NULL	NUMBER(3,0)
	The I1 SPECIES PERCENT 2 is the estimate of given inventory "uneven-aged Layer 1-Mature" component tree species percentage within the forest cover polygon.		
650	I1_SPECIES_AGE_2	NULL	NUMBER(5,0)
	The I1 SPECIES AGE 2 is the average age of the given inventory "uneven-aged Layer 1-Mature" component tree species percent within the forest cover polygon		
660	I1_SPECIES_HEIGHT_2	NULL	NUMBER(3,1)
	The I1 SPECIES HEIGHT 2 is the average height of the given inventory "uneven-aged Layer 1-Mature" component leading tree species in metres.		
670	I1_SPECIES_CODE_3	NULL	VARCHAR2(8)
	The I1 SPECIES CODE 3 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 1-Mature" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
680	I1_SPECIES_PERCENT_3	NULL	NUMBER(3,0)
	The I1 SPECIES PERCENT 3 is an estimate of given inventory "uneven-aged Layer 1-Mature" component tree species percentage within the forest cover polygon.		
690	I1_SPECIES_CODE_4	NULL	VARCHAR2(8)
	The I1 SPECIES CODE 4 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 1-Mature" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		

Table: RSLT_FOREST_COVER_INV_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
700	I1_SPECIES_PERCENT_4	NULL	NUMBER(3,0)
	The I1 SPECIES PERCENT 4 is the estimate of given inventory "uneven-aged Layer 1-Mature" component tree species percentage within the forest cover polygon.		
710	I1_SPECIES_CODE_5	NULL	VARCHAR2(8)
	The I1 SPECIES CODE 5 representing the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 1-Mature" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
720	I1_SPECIES_PERCENT_5	NULL	NUMBER(3,0)
	The I1 SPECIES PERCENT 5 is an estimate of given inventory "uneven-aged Layer 1-Mature" component tree species percentage within the forest cover polygon.		
730	I1_MORE_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	The I1 INV LABEL is 'Y' when this layer contains more than 5 species records; these records are available in RSLT_FOREST_COVER_SPECIES.		
740	I1_INV_LABEL	NULL	VARCHAR2(160)
	The I1 MORE SPECIES EXIST IND is the Inventory Label for "uneven-aged Layer 1-Mature" forest cover polygon		
750	I2_FOREST_COVER_LAYER_ID	NULL	NUMBER(10,0)
	The I2 FOREST COVER LAYER ID is a RESULTS system-generated unique identifer for the layer information.		
760	I2_TOTAL_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I2 TOTAL STEMS PER HA is the Total stems per hectare for the "uneven-aged Layer 2-Pole" forest cover polygon.		
770	I2_TOTAL_WELL_SPACED_STEMS_HA	NULL	NUMBER(10,0)
	The I2 TOTAL WELL SPACED STEMS HA is the total number of well-spaced stems per hectare for the "uneven-aged Layer 2-Pole" forest cover polygon. Stems density for silviculture layer disregarding the M-value.		
780	I2_WELL_SPACED_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I2 TOTAL WELL SPACED STEMS HA is the number of well-spaced stems per hectare for "uneven-aged Layer 2-Pole" forest cover polygon. Trees are healthy, preferred or acceptable species and well - spaced using the minimum inter-tree distance in the stocking standards (as deifned by the SU Identifier).		
790	I2_FREE_GROWING_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I2 FREE GROWING STEMS PER HA is the number of free-growing stems per hectare for "uneven-aged Layer 2-Pole" forest cover polygon. Free gorwing stem density for the silviculture (based on the M-value). Free growing trees are healthy, preferred, or acceptable species, well-spaced, free from inhibiting brush, and meet or exceed the minimum height (if applicable).		
800	I2_CROWN_CLOSURE_PERCENT	NULL	NUMBER(3,0)
	The I2 CROWN CLOSURE PERCENT represents the closing together of the crowns of trees in a forest as they age and grow effectively blocking sunlight from reaching the forest floor for "uneven-aged Layer 2-Pole" forest cover polygon.		
810	I2_BASAL_AREA	NULL	NUMBER(5,0)
	The I2 BASAL AREA is the cumulative cross-sectional residual basal area (in hectares) of all stems >12.5cm dbh for "uneven-aged Layer 2-Pole" forest cover polygon. Required if basal area is a part of stocking standard.		
830	I2_SPECIES_CODE_1	NULL	VARCHAR2(8)
	The I2 SPECIES CODE 1 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 2-Pole" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
840	I2_SPECIES_PERCENT_1	NULL	NUMBER(3,0)
	The I2 SPECIES PERCENT 1 is the estimate of given inventory "uneven-aged Layer 2-Pole" component tree species percentage within the forest cover polygon.		
850	I2_SPECIES_AGE_1	NULL	NUMBER(5,0)
	The I2 SPECIES AGE 1 is the average age of the given inventory "uneven-aged Layer 2-Pole" component tree species percent within the forest cover polygon		
860	I2_SPECIES_HEIGHT_1	NULL	NUMBER(3,1)
	The I2 SPECIES HEIGHT 1 is the average height of the given inventory "uneven-aged Layer 2-Pole" component leading tree species in metres.		
870	I2_SPECIES_CODE_2	NULL	VARCHAR2(8)

Table: RSLT_FOREST_COVER_INV_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	The I2 SPECIES CODE 2 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 2-Pole" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
880	I2_SPECIES_PERCENT_2	NULL	NUMBER(3,0)
	The I2 SPECIES PERCENT 2 is the estimate of given inventory "uneven-aged Layer 2-Pole" component tree species percentage within the forest cover polygon.		
890	I2_SPECIES_AGE_2	NULL	NUMBER(5,0)
	The I2 SPECIES AGE 2 is the average age of the given inventory "uneven-aged Layer 2-Pole" component tree species percent within the forest cover polygon		
900	I2_SPECIES_HEIGHT_2	NULL	NUMBER(3,1)
	The I2 SPECIES HEIGHT 2 is the average height of the given inventory "uneven-aged Layer 2-Pole" component leading tree species in metres.		
910	I2_SPECIES_CODE_3	NULL	VARCHAR2(8)
	The I2 SPECIES CODE 3 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 2-Pole" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
920	I2_SPECIES_PERCENT_3	NULL	NUMBER(3,0)
	The I2 SPECIES PERCENT 3 is the estimate of given inventory "uneven-aged Layer 2-Pole" component tree species percentage within the forest cover polygon.		
930	I2_SPECIES_CODE_4	NULL	VARCHAR2(8)
	The I2 SPECIES CODE 4 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 2-Pole" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
940	I2_SPECIES_PERCENT_4	NULL	NUMBER(3,0)
	The I2 SPECIES PERCENT 4 is the estimate of given inventory "uneven-aged Layer 2-Pole" component tree species percentage within the forest cover polygon.		
950	I2_SPECIES_CODE_5	NULL	VARCHAR2(8)
	The I2 SPECIES CODE 5 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 2-Pole" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
960	I2_SPECIES_PERCENT_5	NULL	NUMBER(3,0)
	The I2 SPECIES PERCENT 5 is the estimate of given inventory "uneven-aged Layer 2-Pole" component tree species percentage within the forest cover polygon.		
970	I2_MORE_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	The I2 MORE SPECIES EXIST IND is 'Y' when this layer contains more than 5 species records; these records are available in RSLT_FOREST_COVER_SPECIES.		
980	I2_INV_LABEL	NULL	VARCHAR2(160)
	The I2 INV LABEL is the Inventory Label for "uneven-aged Layer 2-Pole" forest cover polygon		
990	I3_FOREST_COVER_LAYER_ID	NULL	NUMBER(10,0)
	The I3 FOREST COVER LABEL ID is a RESULTS system-generated unique identifer for the layer information.		
1000	I3_TOTAL_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I3 TOTAL STEMS PER HA is the total stems per hectare for the "uneven-aged Layer 3-Sapling" forest cover polygon.		
1010	I3_TOTAL_WELL_SPACED_STEMS_HA	NULL	NUMBER(10,0)
	The I3 TOTAL WELL SPACED STEMS HA is the total number of well-spaced stems per hectare for the "uneven-aged Layer 3-Sapling" forest cover polygon. Stems density for silviculture layer disregarding the M-value.		
1020	I3_WELL_SPACED_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I3 WELL SPACED STEMS PER HA is the number of well-spaced stems per hectare for "uneven-aged Layer 3-Sapling" forest cover polygon. Trees are healthy, preferred or acceptable species and well - spaced using the minimum inter-tree distance in the stocking standards (as deifned by the SU Identifier).		
1030	I3_FREE_GROWING_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I3 FREE GROWING STEMS PER HA is the number of free-growing stems per hectare for "uneven-aged Layer 3-Sapling" forest cover polygon. Free gorwing stem density for the silviculture (based on the M-value). Free growing trees are healthy, preferred, or acceptable species, well-spaced, free from inhibiting brush, and meet or exceed the minimum height (if applicable).		

Table: RSLT_FOREST_COVER_INV_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
1040	I3_CROWN_CLOSURE_PERCENT	NULL	NUMBER(3,0)
	The I3 CROWN CLOSURE PERCENT represents the closing together of the crowns of trees in a forest as they age and grow effectively blocking sunlight from reaching the forest floor for "uneven-aged Layer 3-Sapling" forest cover polygon.		
1050	I3_BASAL_AREA	NULL	NUMBER(5,0)
	The I3 BASAL AREA is the cumulative cross-sectional residual basal area (in hectares) of all stems >12.5cm dbh for "uneven-aged Layer 3-Sapling" forest cover polygon. Required if basal area is a part of stocking standard.		
1070	I3_SPECIES_CODE_1	NULL	VARCHAR2(8)
	The I3 SPECIES CODE 1 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 3-Sapling" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
1080	I3_SPECIES_PERCENT_1	NULL	NUMBER(3,0)
	The I3 SPECIES PERCENT 1 is the estimate of given inventory "uneven-aged Layer 3-Sapling" component tree species percentage within the forest cover polygon.		
1090	I3_SPECIES_AGE_1	NULL	NUMBER(5,0)
	The I3 SPECIES AGE 1 is the average age of the given inventory "uneven-aged Layer 3-Sapling" component tree species percent within the forest cover polygon		
1100	I3_SPECIES_HEIGHT_1	NULL	NUMBER(3,1)
	The I3 SPECIES HEIGHT 1 is the average height of the given inventory "uneven-aged Layer 3-Sapling" component leading tree species in metres.		
1110	I3_SPECIES_CODE_2	NULL	VARCHAR2(8)
	The I3 SPECIES CODE 2 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 3-Sapling" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
1120	I3_SPECIES_PERCENT_2	NULL	NUMBER(3,0)
	The I3 SPECIES PERCENT 2 is the estimate of given inventory "uneven-aged Layer 3-Sapling" component tree species percentage within the forest cover polygon.		
1130	I3_SPECIES_AGE_2	NULL	NUMBER(5,0)
	The I3 SPECIES AGE 2 is the average age of the given inventory "uneven-aged Layer 3-Sapling" component tree species percent within the forest cover polygon		
1140	I3_SPECIES_HEIGHT_2	NULL	NUMBER(3,1)
	The I3 SPECIES HEIGHT 2 is the average height of the given inventory "uneven-aged Layer 3-Sapling" component leading tree species in metres.		
1150	I3_SPECIES_CODE_3	NULL	VARCHAR2(8)
	The I3 SPECIES CODE 3 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 3-Sapling" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
1160	I3_SPECIES_PERCENT_3	NULL	NUMBER(3,0)
	The I3 SPECIES PERCENT 3 is the estimate of given inventory "uneven-aged Layer 3-Sapling" component tree species percentage within the forest cover polygon.		
1170	I3_SPECIES_CODE_4	NULL	VARCHAR2(8)
	The I3 SPECIES CODE 4 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 3-Sapling" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
1180	I3_SPECIES_PERCENT_4	NULL	NUMBER(3,0)
	The I3 SPECIES PERCENT 4 estimate of given inventory "uneven-aged Layer 3-Sapling" component tree species percentage within the forest cover polygon.		
1190	I3_SPECIES_CODE_5	NULL	VARCHAR2(8)
	The I3 SPECIES CODE 5 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 3-Sapling" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
1200	I3_SPECIES_PERCENT_5	NULL	NUMBER(3,0)
	The I3 SPECIES PERCENT 5 is the estimate of given inventory "uneven-aged Layer 3-Sapling" component tree species percentage within the forest cover polygon.		
1210	I3_MORE_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	The I3 MORE SPECIES EXIST IND is 'Y' when this layer contains more than 5 species records; these		

Table: RSLT_FOREST_COVER_INV_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	records are available in RSLT_FOREST_COVER_SPECIES.		
1220	I3_INV_LABEL	NULL	VARCHAR2(160)
	The I3 INV LABEL is the Inventory Label for "uneven-aged Layer 3-Sapling" forest cover polygon		
1230	I4_FOREST_COVER_LAYER_ID	NULL	NUMBER(10,0)
	The I4 FOREST COVER LAYER ID is a RESULTS system-generated unique identifer for the layer information.		
1240	I4_TOTAL_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I4 TOTAL STEMS PER HA is the total stems per hectare for the "uneven-aged Layer 4-Regen" forest cover polygon.		
1250	I4_TOTAL_WELL_SPACED_STEMS_HA	NULL	NUMBER(10,0)
	The I4 TOTAL WELL SPACED STEMS HA is the total number of well-spaced stems per hectare for the "uneven-aged Layer 4-Regen" forest cover polygon. Stems density for silviculture layer disregarding the M-value.		
1260	I4_WELL_SPACED_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I4 WELL SPACED STEMS PER HA is the number of well-spaced stems per hectare for "uneven-aged Layer 4-Regen" forest cover polygon. Trees are healthy, preferred or acceptable species and well -spaced using the minimum inter-tree distance in the stocking standards (as deifned by the SU Identifier).		
1270	I4_FREE_GROWING_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I4 FREE GROWING STEMS PER HA is the number of free-growing stems per hectare for "uneven-aged Layer 4-Regen" forest cover polygon. Free gorwing stem density for the silviculture (based on the M-value). Free growing trees are healthy, preferred, or acceptable species, well-spaced, free from inhibiting brush, and meet or exceed the minimum height (if applicable).		
1280	I4_CROWN_CLOSURE_PERCENT	NULL	NUMBER(3,0)
	The I4 CROWN CLOSURE PERCENT represents the closing together of the crowns of trees in a forest as they age and grow effectively blocking sunlight from reaching the forest floor for "uneven-aged Layer 4-Regen" forest cover polygon.		
1290	I4_BASAL_AREA	NULL	NUMBER(5,0)
	The I4 BASAL AREA the cumulative cross-sectional residual basal area (in hectares) of all stems >12.5cm dbh for "uneven-aged Layer 4-Regen" forest cover polygon. Required if basal area is a part of stocking standard.		
1310	I4_SPECIES_CODE_1	NULL	VARCHAR2(8)
	The I4 SPECIES PERCENT 1 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 4-Regen" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
1320	I4_SPECIES_PERCENT_1	NULL	NUMBER(3,0)
	The I4 SPECIES PERCENT 1 is the estimate of given inventory "uneven-aged Layer 4-Regen" component tree species percentage within the forest cover polygon.		
1330	I4_SPECIES_AGE_1	NULL	NUMBER(5,0)
	The I4 SPECDIES AGE 1 is the average age of the given inventory "uneven-aged Layer 4-Regen" component tree species percent within the forest cover polygon		
1340	I4_SPECIES_HEIGHT_1	NULL	NUMBER(3,1)
	The I4 SPECIES HEIGHT 1 is the average height of the given inventory "uneven-aged Layer 4-Regen" component leading tree species in metres.		
1350	I4_SPECIES_CODE_2	NULL	VARCHAR2(8)
	The I4 SPECIES CODE represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 4-Regen" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
1360	I4_SPECIES_PERCENT_2	NULL	NUMBER(3,0)
	The I4 SPECIES PERCENT 2 is the estimate of given inventory "uneven-aged Layer 4-Regen" component tree species percentage within the forest cover polygon.		
1370	I4_SPECIES_AGE_2	NULL	NUMBER(5,0)
	The I4 SPECIES AGE 2 is the average age of the given inventory "uneven-aged Layer 4-Regen" component tree species percent within the forest cover polygon		
1380	I4_SPECIES_HEIGHT_2	NULL	NUMBER(3,1)
	The I4 SPECIES HEIGHT 2 is the average height of the given inventory "uneven-aged Layer 4-Regen" component leading tree species in metres.		
1390	I4_SPECIES_CODE_3	NULL	VARCHAR2(8)

Table: RSLT_FOREST_COVER_INV_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	The I4 SPECIES CODE 3 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 4-Regen" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
1400	I4_SPECIES_PERCENT_3	NULL	NUMBER(3,0)
	The I4 SPECIES PERCENT 3 is the estimate of given inventory "uneven-aged Layer 4-Regen" component tree species percentage within the forest cover polygon.		
1410	I4_SPECIES_CODE_4	NULL	VARCHAR2(8)
	The I4 SPECIES PERCENT 4 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 4-Regen" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
1420	I4_SPECIES_PERCENT_4	NULL	NUMBER(3,0)
	The I4 SPECIES PERCENT 4 is the estimate of given inventory "uneven-aged Layer 4-Regen" component tree species percentage within the forest cover polygon.		
1430	I4_SPECIES_CODE_5	NULL	VARCHAR2(8)
	The I4 SPECIES CODE 5 representing the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 4-Regen" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
1440	I4_SPECIES_PERCENT_5	NULL	NUMBER(3,0)
	The I4 SPECIES PERCENT 5 is the estimate of given inventory "uneven-aged Layer 4-Regen" component tree species percentage within the forest cover polygon.		
1450	I4_MORE_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	The I4 MORE SPECIES EXIST IND 'Y' when this layer contains more than 5 species records; these records are available in RSLT_FOREST_COVER_SPECIES.		
1460	I4_INV_LABEL	NULL	VARCHAR2(160)
	The I4 INV LABEL is the Inventory Label for "uneven-aged Layer 4-Regen" forest cover polygon		
1470	GEOMETRY_EXIST_IND	NULL	VARCHAR2(1)
	The GEOMETRY EXIST IND indicates if there is geometry for the opening. A value of 'Y' indicates there is geometry. A value of 'N' indicates there is no geometry.		
1490	FEATURE_AREA	NULL	NUMBER(11,4)
	The FEATURE AREA is the area of the feature in square meters.		
1500	FEATURE_PERIMETER	NULL	NUMBER(11,4)
	The FEATURE PERIMETER is the perimeter of the feature in meters.		
1510	CAPTURE_METHOD_CODE	NULL	VARCHAR2(30)
	The CAPTURE METHOD CODE is a code defining the capture method. (e.g. digitize).		
1520	DATA_SOURCE_CODE	NULL	VARCHAR2(10)
	The DATA SOURCE CODE is a code defining the source of the spatial feature (e.g. GPS, TRIM).		
1530	OBSERVATION_DATE	NULL	DATE
	The OBSERVATION DATE is the geometry collection date.		
1540	DATA_QUALITY_COMMENT	NULL	VARCHAR(255)
	The DATA QUALITY COMMENT is a comment indicating the Geometry accuracy.		
1545	FOREST_COVER_WHO_CREATED	NOT NULL	VARCHAR2(30)
	The FOREST COVER WHO CREATED is the USERID of the individual who created the forest cover record.		
1550	FOREST_COVER_WHEN_CREATED	NOT NULL	DATE
	The FOREST COVER WHO UPDATED is the date and time when the forest cover record was created.		
1550	FOREST_COVER_WHO_UPDATED	NOT NULL	VARCHAR2(30)
	The FOREST COVER WHEN UPDATED is the USERID of the individual who last updated the forest cover record.		
1560	FOREST_COVER_WHEN_UPDATED	NOT NULL	DATE
	THE FOREST COVER WHEN UPDATED is the date and time when the forest cover record was last updated.		
1570	CHANGE_TIMESTAMP1	NOT NULL	DATE
	The date and time of the last update to the FOREST COVER table.		
1580	CHANGE_TIMESTAMP2	NULL	DATE
	The date and time of the last update to the STOCKING STANDARD UNIT table.		
1590	CHANGE_TIMESTAMP3	NULL	DATE
	The date and time of the last update to the FOREST COVER GEOMETRY table.		

Table: RSLT_FOREST_COVER_INV_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
1600	CHANGE_TIMESTAMP4	NULL	DATE
	The date and time of the last update to the FOREST COVER LAYER table.		
1610	CHANGE_TIMESTAMP5	NULL	DATE
	The date and time of the last update to the FOREST COVER SPECIES table.		
1630	CHANGE_COUNT1	NULL	NUMBER(2)
	A count of all of the FOREST COVER LAYER records that relate to this record.		
1640	CHANGE_COUNT2	NULL	NUMBER(2)
	A count of all of the FOREST COVER SPECIES records that relate to this record.		
1650	FEATURE_CLASS_SKEY	NULL	NUMBER(10,0)
	The FEATURE CLASS SKEY is the unique key assigned to a Feature Class by the Ministry of Forests.		
1660	GEOMETRY	NULL	
	The GEOMETRY is the Forest Cover geographical representation.		
1670	OBJECTID	NOT NULL	INTEGER
	The OBJECTID is a system generated value uniquely identifying the opening. Used by SDE.		

Unique Constraints:

RSLT_FCI_UK
  OBJECTID

Foreign Keys:

RSLT_FCI_RSLT_OPEN_FK
  OPENING_ID = RSLT_OPENING_POLYGON.OPENING_ID
RSLT_FCI_RSLT_SU_FK
  STOCKING_STANDARD_UNIT_ID = RSLT_STANDARDS_UNIT_POLY.STOCKING_STANDARD_UNIT_ID

Indexes:

RSLT_FCI_GEOM_I
  GEOMETRY
RSLT_FCI_RSLT_OPEN_FK_I
  OPENING_ID
RSLT_FCI_RSLT_SU_FK_I
  STOCKING_STANDARD_UNIT_ID

Table: RSLT_FOREST_COVER_INV_SVW

Description:

Spatial representation of the opening's forest cover attributes. The attributes have been denormalized and are limited to the Inventory attribution of the Forest Cover Polygon.

Columns:

Seq.	Column	Nulls?	Type
10	FOREST_COVER_ID	NOT NULL	NUMBER(10,0)
	The FOREST COVER ID is a system-generated value by RESULTS to uniquely identify forest cover polygon.		
20	STOCKING_STANDARD_UNIT_ID	NULL	NUMBER(10,0)
	The STOCKING STANDARD UNIT ID is a system-generated value by RESULTS to uniquely identify standards units.		
30	OPENING_ID	NOT NULL	NUMBER(10,0)
	The OPENING ID is a system generated value by RESULTS to uniquely identify the opening.		
40	STANDARDS_UNIT_ID	NULL	VARCHAR2(4)
	The STANDARDS UNIT ID is an assigned unique identifier that respresents the standards units. The SU that forest cover polygon is assocated with.		
50	SILV_POLYGON_NUMBER	NULL	VARCHAR2(30)
	The SILV POLYGON NUMBER is an assigned unique identifer that represents the forest cover polygon.		
60	SILV_POLYGON_AREA	NOT NULL	NUMBER(7,1)
	The SILV POLYGON AREA is the total area in hectares occupied by each polygon. The sum of all areas for a polygon(s) should not be greater than the opening gross area.		
70	SILV_POLYGON_NET_AREA	NOT NULL	NUMBER(7,1)
	The SILV POLYGON NET AREA is the number of hectares occupied by each polygon. The silviculture polygon net area is the silviculture polygon area minus the sum of all the associated non-mappable areas reported within the forest cover polygon.		
80	SILV_NON_MAPPED_AREA	NOT NULL	NUMBER(7,1)
	The SILV NON MAPPED AREA represents the sum of the total non-mappable area (in hectares) reported within each forest cover polygon.		
90	STOCKING_STATUS_CODE	NULL	VARCHAR2(3)
	The STOCKING STATUS CODE is an indication of growing space occupancy relative to establish standard. Status refers to whether the site has met those standards. Stocking status is most often described as NSR-not satisfactorily restocked, IMM-immature, MAT-mature.		
100	STOCKING_TYPE_CODE	NULL	VARCHAR2(3)
	The STOCKING TYPE CODE is a further classification of stocking status for the polygon. Eg. NAT-natural, PL-planting, etc.		
110	STOCKING_CLASS_CODE	NULL	VARCHAR2(1)
	The STOCKING CLASS CODE represents a numeric code representing a range of stems per hectares. Examples: stocking class 0 is immature; stocking class 1 is mature with 76+ stems/ha > 27.5dbh.		
120	SILV_RESERVE_CODE	NULL	VARCHAR2(1)
	The SILV RESERVE CODE identifies the spatial pattern of a reserve of retention area associated with a silvicultural system. Reserves are forest patches or individual trees retained during harvesting, or other forestry opereations to provide habitat, scenic, biodiversity, and other values. Examples R-Riparian Reserve; W-Wildlife Tree Patch Reserve; etc.		
130	SILV_RESERVE_OBJECTIVE_CODE	NULL	VARCHAR2(3)
	The SILV RESERVE OBJECTIVE CODE refers to the managmenet goal of the reserve. Examples: WTR-Wildlife Tree Retention; RMA-Riparian reserve, etc.		
140	TREE_COVER_PATTERN_CODE	NULL	VARCHAR2(1)
	The TREE COVER PATTERN CODE is the spatial arrangement of residual patches of overstorey (Layer 1). Applies to polygons in which trees are retained as apart of the silvicultural system or disturbance characteristic (eg. stands with overstorey). Examples: 9-Continuous occurrence with very few inclusions.; 8-Continuous occurrence with several inclusions.; etc.		
150	REENTRY_YEAR	NULL	NUMBER(4,0)
	The RE-ENTRY YEAR is the year the next harvest entry is expected to occur in the opening. Applies to partial-cut silvicultural systems.		
160	REFERENCE_YEAR	NOT NULL	NUMBER(4,0)
	The REFERENCE YEAR is the year the forest cover polygon data were collected.		
170	SITE_INDEX	NULL	NUMBER(5,0)
	The SITE INDEX is a measure of forest land productivity. Enter the projected average height in metres of		

Table: RSLT_FOREST_COVER_INV_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	the leading species of the forest cover inventory at 50 years after the stands achieves breast height (1.3m).		
180	SITE_INDEX_SOURCE_CODE	NULL	VARCHAR2(1)
	The SITE INDEX SOURCE CODE is a source or origin of the site index. Example: C-site index from site index curve.		
190	BGC_ZONE_CODE	NULL	VARCHAR2(4)
	The BGC_ZONE_CODE of the Standards Unit, according to the Biogeocmlimatic Ecosystem Classification (BEC) system. Eg. IDF; MS; CWH.		
200	BGC_SUBZONE_CODE	NULL	VARCHAR2(3)
	The BGC SUBZONE CODE of the Standards Unit, according to the BEC system. Eg. dk; xc; mk.		
210	BGC_VARIANT	NULL	VARCHAR2(1)
	The BGC VARIANT according to the BEC system. Eg. 1, 2. A division of the BGC Subzone on the basis of differences in floristic composition of the zonal ecosystem, but usually on the basis of differences in the cover and vigour of the plant species.		
220	BGC_PHASE	NULL	VARCHAR2(1)
	The BGC PHASE, according to the BEC system. Accomodates the variation, resulting from local relief, in the regional climate of the subzones and variants.		
230	BEC_SITE_SERIES	NULL	VARCHAR2(4)
	The Site series for the given biogeoclimatic unit, according to the BEC system. Eg. 01, 04, 05. Site series is the consideration of all ecosystems capable of producing vegetation belonging to the same plant association at climax.		
240	BEC_SITE_TYPE	NULL	VARCHAR2(3)
	The BEC SITE TYPE for certain site series, according to the BEC system. Site type is the partitionment of the site series according to one or more critical site factors thought to affect ecosystem response to management treatments. Eg. MS, NP.		
250	BEC_SERAL	NULL	VARCHAR2(4)
	The BEC SERAL (often termed successional) classification in BEC is an integration of site and vegetation classifications with structural stage development. Eg. Accp, Acho.		
260	FOREST_COVER_INV_TYPE	NULL	VARCHAR2(7)
	The FOREST COVER INV TYPE describes the forest cover stand type characteristics: EVEN, UNEVEN, NONE and UNKOWN.		
270	I_FOREST_COVER_LAYER_ID	NULL	NUMBER(10,0)
	The FOREST COVER LAYER ID is a RESULTS system-generated unique identifer for the layer information.		
280	I_TOTAL_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I TOTAL STEMS PER HA is the total stems per hectare for the "even-aged" forest cover polygon.		
290	I_TOTAL_WELL_SPACED_STEMS_HA	NULL	NUMBER(10,0)
	The I TOTAL WELL SPACED STEMS HA is the total number of well-spaced stems per hectare for the "even-aged" forest cover polygon. Stems density for silviculture layer disregarding the M-value.		
300	I_WELL_SPACED_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I WELL SPACED STEMS PER HA is the number of well-spaced stems per hectare for "even-aged" forest cover polygon. Trees are healthy, preferred or acceptable species and well -spaced using the minimum inter-tree distance in the stocking standards (as deifned by the SU Identifier).		
310	I_FREE_GROWING_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I FREE GROWING STEMS PER HA is the number of free-growing stems per hectare for "even-aged" forest cover polygon. Free gorwing stem density for the silviculture (based on the M-value). Free growing trees are healthy, preferred, or acceptable species, well-spaced, free from inhibiting brush, and meet or exceed the minimum height (if applicable).		
320	I_CROWN_CLOSURE_PERCENT	NULL	NUMBER(3,0)
	The I CROWN CLOSURE PERCENT represents the closing together of the crowns of trees in a forest as they age and grow effectively blocking sunlight from reaching the forest floor for "even-aged" forest cover polygon.		
330	I_BASAL_AREA	NULL	NUMBER(5,0)
	The I BASAL AREA is the cumulative cross-sectional residual basal area (in hectares) of all stems >12.5cm dbh for "even-aged" forest cover polygon. Required if basal area is a part of stocking standard.		
340	I_SPECIES_CODE_1	NULL	VARCHAR2(8)
	The I SPECIES CODE 1 represents the tree species (primary, secondary, tertiary, etc.) with the forest		

Table: RSLT_FOREST_COVER_INV_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	cover polygon for the inventory "even-aged" component		
350	I_SPECIES_PERCENT_1	NULL	NUMBER(3,0)
	The I SPECIES PERCENT 1 is the estimate of given inventory "even-aged" component tree species percentage within the forest cover polygon.		
360	I_SPECIES_AGE_1	NULL	NUMBER(5,0)
	The I SPECIES AGE 1 is the average age of the given inventory "even-aged" component tree species percent within the forest cover polygon		
370	I_SPECIES_HEIGHT_1	NULL	NUMBER(3,1)
	The I SPECIES HEIGHT 1 is the average height of the given inventory "even-aged" component leading tree species in metres.		
380	I_SPECIES_CODE_2	NULL	VARCHAR2(8)
	The I SPECIES CODE 2 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "even-aged" component		
390	I_SPECIES_PERCENT_2	NULL	NUMBER(3,0)
	The I SPECIES PERCENT 2 is the estimate of given inventory "even-aged" component tree species percentage within the forest cover polygon.		
400	I_SPECIES_AGE_2	NULL	NUMBER(5,0)
	The I SPECIES AGE 2 is the average age of the given inventory "even-aged" component tree species percent within the forest cover polygon		
410	I_SPECIES_HEIGHT_2	NULL	NUMBER(3,1)
	The I SPECIES HEIGHT 2 is the average height of the given inventory "even-aged" component leading tree species in metres.		
420	I_SPECIES_CODE_3	NULL	VARCHAR2(8)
	The I SPECIES CODE 3 is the Tree Species Code representing the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "even-aged" component		
430	I_SPECIES_PERCENT_3	NULL	NUMBER(3,0)
	The I SPECIES PERCENT 3 is the estimate of given inventory "even-aged" component tree species percentage within the forest cover polygon.		
440	I_SPECIES_CODE_4	NULL	VARCHAR2(8)
	The I SPECIES CODE 4 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "even-aged" component		
450	I_SPECIES_PERCENT_4	NULL	NUMBER(3,0)
	The I SPECIES PERCENT 4 is the estimate of given inventory "even-aged" component tree species percentage within the forest cover polygon.		
460	I_SPECIES_CODE_5	NULL	VARCHAR2(8)
	The I SPECIES CODE 5 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "even-aged" component		
470	I_SPECIES_PERCENT_5	NULL	NUMBER(3,0)
	The I SPECIES PERCENT 5 is the estimate of given inventory "even-aged" component tree species percentage within the forest cover polygon.		
480	I_MORE_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	The I MORE SPECIES EXIST IND is 'Y' when this layer contains more than 5 species records; these records are available in RSLT_FOREST_COVER_SPECIES		
490	I_INV_LABEL	NULL	VARCHAR2(160)
	The I INV LABEL is the Inventory Label for "even-aged" forest cover polygon		
500	I1_FOREST_COVER_LAYER_ID	NULL	NUMBER(10,0)
	The I1 FOREST COVER LAYER ID is a RESULTS system-generated unique identifer for the layer information.		
510	I1_TOTAL_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I1 TOTAL STEMS PER HA is the stems per hectare for the "uneven-aged Layer 2-Pole" forest cover polygon.		
520	I1_TOTAL_WELL_SPACED_STEMS_HA	NULL	NUMBER(10,0)
	The I1 TOTAL WELL SPACED STEMS HA is the Total number of well-spaced stems per hectare for the "uneven-aged Layer 1-Mature" forest cover polygon. Stems density for silviculture layer disregarding the M-value.		
530	I1_WELL_SPACED_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I1 WELL SPACED STEMS PER HA is the number of well-spaced stems per hectare for "uneven-aged		

Table: RSLT_FOREST_COVER_INV_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	Layer 1-Mature" forest cover polygon. Trees are healthy, preferred or acceptable species and well -spaced using the minimum inter-tree distance in the stocking standards (as deifned by the SU Identifier).		
540	I1_FREE_GROWING_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I FREE GROWING STEMS PER HA is the number of free-growing stems per hectare for "even-aged" forest cover polygon. Free growing stem density for the silviculture (based on the M-value). Free growing trees are healthy, preferred, or acceptable species, well-spaced, free from inhibiting brush, and meet or exceed the minimum height (if applicable).		
550	I1_CROWN_CLOSURE_PERCENT	NULL	NUMBER(3,0)
	The I1 CROWN CLOSURE PERCENT represents the closing together of the crowns of trees in a forest as they age and grow effectively blocking sunlight from reaching the forest floor for "uneven-aged Layer 1-Mature" forest cover polygon.		
560	I1_BASAL_AREA	NULL	NUMBER(5,0)
	The I1 BASAL AREA is the cumulative cross-sectional residual basal area of all stems >12.5cm dbh for "uneven-aged Layer 1-Mature" forest cover polygon. Required if basal area is a part of stocking standard.		
570	I1_SPECIES_CODE_1	NULL	VARCHAR2(8)
	The I1 SPECIES CODE 1 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 1-Mature" component		
580	I1_SPECIES_PERCENT_1	NULL	NUMBER(3,0)
	The I1 SPECIES PERCENT 1 is the estimate of given inventory "uneven-aged Layer 1-Mature" component tree species percentage within the forest cover polygon.		
590	I1_SPECIES_AGE_1	NULL	NUMBER(5,0)
	The I1 SPECIES AGE 1 is the average age of the given inventory "uneven-aged Layer 1-Mature" component tree species percent within the forest cover polygon		
600	I1_SPECIES_HEIGHT_1	NULL	NUMBER(3,1)
	The I1 SPECIES HEIGHT 1 is the average height of the given inventory "uneven-aged Layer 1-Mature" component leading tree species in metres.		
610	I1_SPECIES_CODE_2	NULL	VARCHAR2(8)
	The I1 SPECIES CODE 2 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 1-Mature" component		
620	I1_SPECIES_PERCENT_2	NULL	NUMBER(3,0)
	The I1 SPECIES PERCENT 2 is the estimate of given inventory "uneven-aged Layer 1-Mature" component tree species percentage within the forest cover polygon.		
630	I1_SPECIES_AGE_2	NULL	NUMBER(5,0)
	The I1 SPECIES AGE 2 is the average age of the given inventory "uneven-aged Layer 1-Mature" component tree species percent within the forest cover polygon		
640	I1_SPECIES_HEIGHT_2	NULL	NUMBER(3,1)
	The I1 SPECIES HEIGHT 2 is the average height of the given inventory "uneven-aged Layer 1-Mature" component leading tree species in metres.		
650	I1_SPECIES_CODE_3	NULL	VARCHAR2(8)
	The I1 SPECIES CODE 3 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 1-Mature" component		
660	I1_SPECIES_PERCENT_3	NULL	NUMBER(3,0)
	The I1 SPECIES PERCENT 3 is an estimate of given inventory "uneven-aged Layer 1-Mature" component tree species percentage within the forest cover polygon.		
670	I1_SPECIES_CODE_4	NULL	VARCHAR2(8)
	The I1 SPECIES CODE 4 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 1-Mature" component		
680	I1_SPECIES_PERCENT_4	NULL	NUMBER(3,0)
	The I1 SPECIES PERCENT 4 is the estimate of given inventory "uneven-aged Layer 1-Mature" component tree species percentage within the forest cover polygon.		
690	I1_SPECIES_CODE_5	NULL	VARCHAR2(8)
	The I1 SPECIES CODE 5 representing the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 1-Mature" component		
700	I1_SPECIES_PERCENT_5	NULL	NUMBER(3,0)
	The I1 SPECIES PERCENT 5 is an estimate of given inventory "uneven-aged Layer 1-Mature" component tree species percentage within the forest cover polygon.		
710	I1_MORE_SPECIES_EXIST_IND	NULL	VARCHAR2(1)

Table: RSLT_FOREST_COVER_INV_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	The I1 MORE SPECIES EXIST IND is 'Y' when this layer contains more than 5 species records; these records are available in RSLT FOREST COVER SPECIES.		
720	I1_INV_LABEL	NULL	VARCHAR2(160)
	The I1 INV LABEL is the Inventory Label for "uneven-aged Layer 1-Mature" forest cover polygon		
730	I2_FOREST_COVER_LAYER_ID	NULL	NUMBER(10,0)
	The I2 FOREST COVER LAYER ID is a RESULTS system-generated unique identifer for the layer information.		
740	I2_TOTAL_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I2 TOTAL STEMS PER HA is the Total stems per hectare for the "uneven-aged Layer 2-Pole" forest cover polygon.		
750	I2_TOTAL_WELL_SPACED_STEMS_HA	NULL	NUMBER(10,0)
	The I2 TOTAL WELL SPACED STEMS HA is the total number of well-spaced stems per hectare for the "uneven-aged Layer 2-Pole" forest cover polygon. Stems density for silviculture layer disregarding the M-value.		
760	I2_WELL_SPACED_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I2 TOTAL WELL SPACED STEMS HA is the number of well-spaced stems per hectare for "uneven-aged Layer 2-Pole" forest cover polygon. Trees are healthy, preferred or acceptable species and well - spaced using the minimum inter-tree distance in the stocking standards (as deifned by the SU Identifier).		
770	I2_FREE_GROWING_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I2 FREE GROWING STEMS PER HA is the number of free-growing stems per hectare for "uneven-aged Layer 2-Pole" forest cover polygon. Free gorwing stem density for the silviculture (based on the M-value). Free growing trees are healthy, preferred, or acceptable species, well-spaced, free from inhibiting brush, and meet or exceed the minimum height (if applicable).		
780	I2_CROWN_CLOSURE_PERCENT	NULL	NUMBER(3,0)
	The I2 CROWN CLOSURE PERCENT represents the closing together of the crowns of trees in a forest as they age and grow effectively blocking sunlight from reaching the forest floor for "uneven-aged Layer 2-Pole" forest cover polygon.		
790	I2_BASAL_AREA	NULL	NUMBER(5,0)
	The I2 BASAL AREA is the cumulative cross-sectional residual basal area of all stems >12.5cm dbh for "uneven-aged Layer 2-Pole" forest cover polygon. Required if basal area is a part of stocking standard.		
800	I2_SPECIES_CODE_1	NULL	VARCHAR2(8)
	The I2 SPECIES CODE 1 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 2-Pole" component		
810	I2_SPECIES_PERCENT_1	NULL	NUMBER(3,0)
	The I2 SPECIES PERCENT 1 is the estimate of given inventory "uneven-aged Layer 2-Pole" component tree species percentage within the forest cover polygon.		
820	I2_SPECIES_AGE_1	NULL	NUMBER(5,0)
	The I2 SPECIES AGE 1 is the average age of the given inventory "uneven-aged Layer 2-Pole" component tree species percent within the forest cover polygon		
830	I2_SPECIES_HEIGHT_1	NULL	NUMBER(3,1)
	The I2 SPECIES HEIGHT 1 is the average height of the given inventory "uneven-aged Layer 2-Pole" component leading tree species in metres.		
840	I2_SPECIES_CODE_2	NULL	VARCHAR2(8)
	The I2 SPECIES CODE 2 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 2-Pole" component		
850	I2_SPECIES_PERCENT_2	NULL	NUMBER(3,0)
	The I2 SPECIES PERCENT 2 is the estimate of given inventory "uneven-aged Layer 2-Pole" component tree species percentage within the forest cover polygon.		
860	I2_SPECIES_AGE_2	NULL	NUMBER(5,0)
	The I2 SPECIES AGE 2 is the average age of the given inventory "uneven-aged Layer 2-Pole" component tree species percent within the forest cover polygon		
870	I2_SPECIES_HEIGHT_2	NULL	NUMBER(3,1)
	The I2 SPECIES HEIGHT 2 is the average height of the given inventory "uneven-aged Layer 2-Pole" component leading tree species in metres.		
880	I2_SPECIES_CODE_3	NULL	VARCHAR2(8)
	The I2 SPECIES CODE 3 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 2-Pole" component		

Table: RSLT_FOREST_COVER_INV_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
890	I2_SPECIES_PERCENT_3	NULL	NUMBER(3,0)
	The I2 SPECIES PERCENT 3 is the estimate of given inventory "uneven-aged Layer 2-Pole" component tree species percentage within the forest cover polygon.		
900	I2_SPECIES_CODE_4	NULL	VARCHAR2(8)
	The I2 SPECIES CODE 4 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 2-Pole" component		
910	I2_SPECIES_PERCENT_4	NULL	NUMBER(3,0)
	The I2 SPECIES PERCENT 4 is the estimate of given inventory "uneven-aged Layer 2-Pole" component tree species percentage within the forest cover polygon.		
920	I2_SPECIES_CODE_5	NULL	VARCHAR2(8)
	The I2 SPECIES CODE 5 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 2-Pole" component		
930	I2_SPECIES_PERCENT_5	NULL	NUMBER(3,0)
	The I2 SPECIES PERCENT 5 is the estimate of given inventory "uneven-aged Layer 2-Pole" component tree species percentage within the forest cover polygon.		
940	I2_MORE_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	The I2 MORE SPECIES EXIST IND is 'Y' when this layer contains more than 5 species records; these records are available in RSLT FOREST COVER SPECIES.		
950	I2_INV_LABEL	NULL	VARCHAR2(160)
	The I2 INV LABEL is the Inventory Label for "uneven-aged Layer 2-Pole" forest cover polygon		
960	I3_FOREST_COVER_LAYER_ID	NULL	NUMBER(10,0)
	The I3 FOREST COVER LABEL ID is a RESULTS system-generated unique identifer for the layer information.		
970	I3_TOTAL_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I3 TOTAL STEMS PER HA is the total stems per hectare for the "uneven-aged Layer 3-Sapling" forest cover polygon.		
980	I3_TOTAL_WELL_SPACED_STEMS_HA	NULL	NUMBER(10,0)
	The I3 TOTAL WELL SPACED STEMS HA is the total number of well-spaced stems per hectare for the "uneven-aged Layer 3-Sapling" forest cover polygon. Stems density for silviculture layer disregarding the M-value.		
990	I3_WELL_SPACED_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I3 WELL SPACED STEMS PER HA is the number of well-spaced stems per hectare for "uneven-aged Layer 3-Sapling" forest cover polygon. Trees are healthy, preferred or acceptable species and well - spaced using the minimum inter-tree distance in the stocking standards (as deifned by the SU Identifier).		
1000	I3_FREE_GROWING_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I3 FREE GROWING STEMS PER HA is the number of free-growing stems per hectare for "uneven-aged Layer 3-Sapling" forest cover polygon. Free gorwing stem density for the silviculture (based on the M-value). Free growing trees are healthy, preferred, or acceptable species, well-spaced, free from inhibiting brush, and meet or exceed the minimum height (if applicable).		
1010	I3_CROWN_CLOSURE_PERCENT	NULL	NUMBER(3,0)
	The I3 CROWN CLOSURE PERCENT represents the closing together of the crowns of trees in a forest as they age and grow effectively blocking sunlight from reaching the forest floor for "uneven-aged Layer 3-Sapling" forest cover polygon.		
1020	I3_BASAL_AREA	NULL	NUMBER(5,0)
	The I3 BASAL AREA is the cumulative cross-sectional residual basal area of all stems >12.5cm dbh for "uneven-aged Layer 3-Sapling" forest cover polygon. Required if basal area is a part of stocking standard.		
1030	I3_SPECIES_CODE_1	NULL	VARCHAR2(8)
	The I3 SPECIES CODE 1 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 3-Sapling" component		
1040	I3_SPECIES_PERCENT_1	NULL	NUMBER(3,0)
	The I3 SPECIES PERCENT 1 is the estimate of given inventory "uneven-aged Layer 3-Sapling" component tree species percentage within the forest cover polygon.		
1050	I3_SPECIES_AGE_1	NULL	NUMBER(5,0)
	The I3 SPECIES AGE 1 is the average age of the given inventory "uneven-aged Layer 3-Sapling" component tree species percent within the forest cover polygon		
1060	I3_SPECIES_HEIGHT_1	NULL	NUMBER(3,1)
	The I3 SPECIES HEIGHT 1 is the average height of the given inventory "uneven-aged Layer 3-Sapling"		

Table: RSLT_FOREST_COVER_INV_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	component leading tree species in metres.		
1070	I3_SPECIES_CODE_2	NULL	VARCHAR2(8)
	The I3 SPECIES CODE 2 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 3-Sapling" component		
1080	I3_SPECIES_PERCENT_2	NULL	NUMBER(3,0)
	The I3 SPECIES PERCENT 2 is the estimate of given inventory "uneven-aged Layer 3-Sapling" component tree species percentage within the forest cover polygon.		
1090	I3_SPECIES_AGE_2	NULL	NUMBER(5,0)
	The I3 SPECIES AGE 2 is the average age of the given inventory "uneven-aged Layer 3-Sapling" component tree species percent within the forest cover polygon		
1100	I3_SPECIES_HEIGHT_2	NULL	NUMBER(3,1)
	The I3 SPECIES HEIGHT 2 is the average height of the given inventory "uneven-aged Layer 3-Sapling" component leading tree species in metres.		
1110	I3_SPECIES_CODE_3	NULL	VARCHAR2(8)
	The I3 SPECIES CODE 3 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 3-Sapling" component		
1120	I3_SPECIES_PERCENT_3	NULL	NUMBER(3,0)
	The I3 SPECIES PERCENT 3 is the estimate of given inventory "uneven-aged Layer 3-Sapling" component tree species percentage within the forest cover polygon.		
1130	I3_SPECIES_CODE_4	NULL	VARCHAR2(8)
	The I3 SPECIES CODE 4 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 3-Sapling" component		
1140	I3_SPECIES_PERCENT_4	NULL	NUMBER(3,0)
	The I3 SPECIES PERCENT 4 estimate of given inventory "uneven-aged Layer 3-Sapling" component tree species percentage within the forest cover polygon.		
1150	I3_SPECIES_CODE_5	NULL	VARCHAR2(8)
	The I3 SPECIES CODE 5 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 3-Sapling" component		
1160	I3_SPECIES_PERCENT_5	NULL	NUMBER(3,0)
	The I3 SPECIES PERCENT 5 is the estimate of given inventory "uneven-aged Layer 3-Sapling" component tree species percentage within the forest cover polygon.		
1170	I3_MORE_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	The I3 MORE SPECIES EXIST IND is 'Y' when this layer contains more than 5 species records; these records are available in RSLT FOREST COVER SPECIES.		
1180	I3_INV_LABEL	NULL	VARCHAR2(160)
	The I3 INV LABEL is the Inventory Label for "uneven-aged Layer 3-Sapling" forest cover polygon		
1190	I4_FOREST_COVER_LAYER_ID	NULL	NUMBER(10,0)
	The I4 FOREST COVER LAYER ID is a RESULTS system-generated unique identifer for the layer information.		
1200	I4_TOTAL_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I4 TOTAL STEMS PER HA is the total stems per hectare for the "uneven-aged Layer 4-Regen" forest cover polygon.		
1210	I4_TOTAL_WELL_SPACED_STEMS_HA	NULL	NUMBER(10,0)
	The I4 TOTAL WELL SPACED STEMS HA is the total number of well-spaced stems per hectare for the "uneven-aged Layer 4-Regen" forest cover polygon. Stems density for silviculture layer disregarding the M-value.		
1220	I4_WELL_SPACED_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I4 WELL SPACED STEMS PER HA is the number of well-spaced stems per hectare for "uneven-aged Layer 4-Regen" forest cover polygon. Trees are healthy, preferred or acceptable species and well -spaced using the minimum inter-tree distance in the stocking standards (as deifned by the SU Identifier).		
1230	I4_FREE_GROWING_STEMS_PER_HA	NULL	NUMBER(10,0)
	The I4 FREE GROWING STEMS PER HA is the number of free-growing stems per hectare for "uneven-aged Layer 4-Regen" forest cover polygon. Free gorwing stem density for the silviculture (based on the M-value). Free growing trees are healthy, preferred, or acceptable species, well-spaced, free from inhibiting brush, and meet or exceed the minimum height (if applicable).		
1240	I4_CROWN_CLOSURE_PERCENT	NULL	NUMBER(3,0)
	The I4 CROWN CLOSURE PERCENT represents the closing together of the crowns of trees in a forest as		

Table: RSLT_FOREST_COVER_INV_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	they age and grow effectively blocking sunlight from reaching the forest floor for "uneven-aged Layer 4-Regen" forest cover polygon.		
1250	I4_BASAL_AREA	NULL	NUMBER(5,0)
	The I4 BASAL AREA the cumulative cross-sectional residual basal area of all stems >12.5cm dbh for "uneven-aged Layer 4-Regen" forest cover polygon. Required if basal area is a part of stocking standard.		
1260	I4_SPECIES_CODE_1	NULL	VARCHAR2(8)
	The I4 SPECIES CODE 1 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 4-Regen" component		
1270	I4_SPECIES_PERCENT_1	NULL	NUMBER(3,0)
	The I4 SPECIES PERCENT 1 is the estimate of given inventory "uneven-aged Layer 4-Regen" component tree species percentage within the forest cover polygon.		
1280	I4_SPECIES_AGE_1	NULL	NUMBER(5,0)
	The I4 SPECDIES AGE 1 is the average age of the given inventory "uneven-aged Layer 4-Regen" component tree species percent within the forest cover polygon		
1290	I4_SPECIES_HEIGHT_1	NULL	NUMBER(3,1)
	The I4 SPECIES HEIGHT 1 is the average height of the given inventory "uneven-aged Layer 4-Regen" component leading tree species in metres.		
1300	I4_SPECIES_CODE_2	NULL	VARCHAR2(8)
	The I4 SPECIES CODE represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 4-Regen" component		
1310	I4_SPECIES_PERCENT_2	NULL	NUMBER(3,0)
	The I4 SPECIES PERCENT 2 is the estimate of given inventory "uneven-aged Layer 4-Regen" component tree species percentage within the forest cover polygon.		
1320	I4_SPECIES_AGE_2	NULL	NUMBER(5,0)
	The I4 SPECIES AGE 2 is the average age of the given inventory "uneven-aged Layer 4-Regen" component tree species percent within the forest cover polygon		
1330	I4_SPECIES_HEIGHT_2	NULL	NUMBER(3,1)
	The I4 SPECIES HEIGHT 2 is the average height of the given inventory "uneven-aged Layer 4-Regen" component leading tree species in metres.		
1340	I4_SPECIES_CODE_3	NULL	VARCHAR2(8)
	The I4 SPECIES CODE 3 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 4-Regen" component		
1350	I4_SPECIES_PERCENT_3	NULL	NUMBER(3,0)
	The I4 SPECIES PERCENT 3 is the estimate of given inventory "uneven-aged Layer 4-Regen" component tree species percentage within the forest cover polygon.		
1360	I4_SPECIES_CODE_4	NULL	VARCHAR2(8)
	The I4 SPECIES PERCENT 4 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 4-Regen" component		
1370	I4_SPECIES_PERCENT_4	NULL	NUMBER(3,0)
	The I4 SPECIES PERCENT 4 is the estimate of given inventory "uneven-aged Layer 4-Regen" component tree species percentage within the forest cover polygon.		
1380	I4_SPECIES_CODE_5	NULL	VARCHAR2(8)
	The I4 SPECIES CODE 5 representing the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the inventory "uneven-aged Layer 4-Regen" component		
1390	I4_SPECIES_PERCENT_5	NULL	NUMBER(3,0)
	The I4 SPECIES PERCENT 5 is the estimate of given inventory "uneven-aged Layer 4-Regen" component tree species percentage within the forest cover polygon.		
1400	I4_MORE_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	The I4 MORE SPECIES EXIST IND is 'Y' when this layer contains more than 5 species records; these records are available in RSLT FOREST COVER SPECIES.		
1410	I4_INV_LABEL	NULL	VARCHAR2(160)
	The I4 INV LABEL is the Inventory Label for "uneven-aged Layer 4-Regen" forest cover polygon		
1420	GEOMETRY_EXIST_IND	NULL	VARCHAR2(1)
	The GEOMETRY EXIST IND indicates if there is geometry for the opening. A value of 'Y' indicates there is geometry. A value of 'N' indicates there is no geometry.		
1430	FEATURE_AREA	NULL	NUMBER(11,4)
	The FEATURE AREA is the area of the feature in square meters.		

Table: RSLT_FOREST_COVER_INV_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
1440	FEATURE_PERIMETER	NULL	NUMBER(11,4)
	The FEATURE PERIMETER is the perimeter of the feature in meters.		
1450	CAPTURE_METHOD_CODE	NULL	VARCHAR2(30)
	The CAPTURE METHOD CODE is a code defining the capture method. (e.g. digitize).		
1460	DATA_SOURCE_CODE	NULL	VARCHAR2(10)
	The DATA SOURCE CODE is a code defining the source of the spatial feature (e.g. GPS, TRIM).		
1480	OBSERVATION_DATE	NULL	DATE
	The FEATURE CLASS SKEY is the unique key assigned to a Feature Class by the Ministry of Forests.		
1490	DATA_QUALITY_COMMENT	NULL	VARCHAR(255)
	The DATA QUALITY COMMENT is a comment indicating the Geometry accuracy.		
1500	FOREST_COVER_WHO_CREATED	NOT NULL	VARCHAR2(30)
	The FOREST COVER WHO CREATED is the USERID of the individual who created the forest cover record.		
1510	FOREST_COVER_WHEN_CREATED	NOT NULL	DATE
	The FOREST COVER WHO UPDATED is the date and time when the forest cover record was created.		
1520	FOREST_COVER_WHO_UPDATED	NOT NULL	VARCHAR2(30)
	The FOREST COVER WHEN UPDATED is the USERID of the individual who last updated the forest cover record.		
1540	FOREST_COVER_WHEN_UPDATED	NOT NULL	DATE
	THE FOREST COVER WHEN UPDATED is the date and time when the forest cover record was last updated.		
1544	FEATURE_CLASS_SKEY	NULL	NUMBER(10,0)
	The OBSERVATION DATE is the geometry collection date.		
1545	GEOMETRY	NULL	
	The GEOMETRY is the Forest Cover geographical representation.		
1550	OBJECTID	NOT NULL	NUMBER(10,0)
	The OBJECTID is a system generated value uniquely identifying the opening. Used by SDE.		

Table: RSLT_FOREST_COVER_RESERVE_POLY

Description:

The spatial representation of a reserve of retention area associated with a silvicultural system. Reserves are forest patches or individual trees retained during harvesting, or other forestry opereations to provide habitat, scenic, biodiversity, and other values. The reserve types included are Riparian, Wildlife Tree Patches, and Other.

Columns:

Seq.	Column	Nulls?	Type
* 10	FOREST_COVER_ID	NOT NULL	NUMBER(10,0)
	The FOREST COVER ID is a system-generated value by RESULTS to uniquely identify forest cover polygon.		
20	OPENING_ID	NOT NULL	NUMBER(10,0)
	The OPENING ID is a system generated value by RESULTS to uniquely identify the opening.		
30	FOREST_FILE_ID	NULL	VARCHAR2(10)
	The FOREST FILE ID represents the licence number of the opening corresponding to the cutting authority. Note where there is more than one tenure associated with the opening, the prime licence is shown. Eg. TFL49, A19204, W0014.		
40	CUTTING_PERMIT_ID	NULL	VARCHAR2(3)
	The CUTTING PERMIT ID corresponds to the licence in the cutting permit document. Note where there is more than one tenure associated with the opening, the prime licence is shown. Eg. TFL49, A19204, W0014.		
50	CUT_BLOCK_ID	NULL	VARCHAR2(10)
	The CUT BLOCK ID is the approved cutblock identifier for the opening as the legal Exhibit 'A' document. Note where there is more than one tenure associated with the opening, the prime licence is shown. Eg. 1002LM		
60	SILV_POLYGON_NO	NOT NULL	VARCHAR2(30)
	The SILV POLYGON NO is an assigned unique identifer that represents the forest cover polygon. *2002/12/20 DM Changed name from SILV POLYGON NO to SILV POLYGON STRATA NO* *2003/01/08 HS Changed name back to SILV POLYGON NO* *Feb 12 2003 wc Changed from Mandatory to Optional* *2004/03/10 R.A.Robb Changed maxlength from 4 to 30*		
70	SILV_POLYGON_AREA	NOT NULL	NUMBER(7,1)
	The SILV POLYGON AREA is the total area in hectares occupied by each polygon. The sum of all areas for a polygon(s) should not be greater than the opening gross area.		
80	SILV_RESERVE_CODE	NULL	VARCHAR2(1)
	The SILV RESERVE CODE identifies the spatial pattern of a reserve of retention area associated with a silvicultural system. Reserves are forest patches or individual trees retained during harvesting, or other forestry opereations to provide habitat, scenic, biodiversity, and other values. Examples R-Riparian Reserve; W-Wildlife Tree Patch Reserve; etc. *Feb 12 2003 wc Changed from Mandatory to Optional*		
90	SILV_RESERVE_OBJECTIVE_CODE	NULL	VARCHAR2(3)
	The SILV RESERVE OBJECTIVE CODE refers to the managmenet goal of the reserve. Examples: WTR-Wildlife Tree Retention; RMA-Riparian reserve, etc. *Jan 23 2003 wc Changed name from SILV_RES_OBJ_CODE to SILV_RESERVE_OBJECTIVE_CODE* *Feb 12 2003 wc Changed from Mandatory to Optional*		
100	ENTRY_USERID	NOT NULL	VARCHAR2(30)
	The USERID of the individual who entered the information.		
110	CHANGE_TIMESTAMP1	NOT NULL	DATE
	The date and time of the last update to the FOREST COVER table.		
120	CHANGE_TIMESTAMP2	NOT NULL	DATE
	The date and time of the last update to the FOREST COVER GEOMETRY table.		
130	GEOMETRY	NULL	
	The GEOMETRY is the Forest Cover Geographical representation.		
140	OBJECTID	NOT NULL	INTEGER
	System generated value uniquely identifying the Forest Cover Reserve. This column is used by SDE.		

Unique Constraints:

RSLT_FCR_UK
OBJECTID

Table: RSLT_FOREST_COVER_RESERVE_POLY (cont'd)

Foreign Keys:

RSLT_FCR_RSLT_OPEN_FK
OPENING_ID = RSLT_OPENING_POLYGON.OPENING_ID

Indexes:

RSLT_FCR_CB_I
FOREST_FILE_ID
CUTTING_PERMIT_ID
CUT_BLOCK_ID
RSLT_FCR_GEOM_I
GEOMETRY
RSLT_FCR_RSLT_OPEN_FK_I
OPENING_ID

Table: RSLT_FOREST_COVER_RESERVE_SVW

Description:

The spatial representation of a reserve of retention area associated with a silvicultural system. Reserves are forest patches or individual trees retained during harvesting, or other forestry opereations to provide habitat, scenic, biodiversity, and other values. The reserve types included are Riparian, Wildlife Tree Patches, and Other.

Columns:

Seq.	Column	Nulls?	Type
10	OPENING_ID	NOT NULL	NUMBER(10,0)
	The OPENING ID is a system generated value by RESULTS to uniquely identify the opening.		
20	FOREST_FILE_ID	NULL	VARCHAR2(10)
	The FOREST FILE ID represents the licence number of the opening corresponding to the cutting authority. Note where there is more than one tenure associated with the opening, the prime licence is shown. Eg. TFL49, A19204, W0014.		
30	CUTTING_PERMIT_ID	NULL	VARCHAR2(3)
	The CUTTING PERMIT ID corresponds to the licence in the cutting permit document. Note where there is more than one tenure associated with the opening, the prime licence is shown. Eg. TFL49, A19204, W0014.		
40	CUT_BLOCK_ID	NULL	VARCHAR2(10)
	The CUT BLOCK ID is the approved cutblock identifier for the opening as the legal Exhibit 'A' document. Note where there is more than one tenure associated with the opening, the prime licence is shown. Eg. 1002LM		
50	SILV_POLYGON_NO	NULL	VARCHAR2(30)
	The SILV POLYGON NO is an assigned unique identifer that represents the forest cover polygon.		
60	SILV_POLYGON_AREA	NULL	NUMBER(7,1)
	The SILV POLYGON AREA is the total area in hectares occupied by each polygon. The sum of all areas for a polygon(s) should not be greater than the opening gross area.		
70	SILV_RESERVE_CODE	NULL	VARCHAR2(1)
	The SILV RESERVE CODE identifies the spatial pattern of a reserve of retention area associated with a silvicultural system. Reserves are forest patches or individual trees retained during harvesting, or other forestry opereations to provide habitat, scenic, biodiversity, and other values.		
80	SILV_RESERVE_OBJECTIVE_CODE	NULL	VARCHAR2(3)
	The SILV RESERVE OBJECTIVE CODE refers to the managmenet goal of the reserve. Examples: WTR-Wildlife Tree Retention; RMA-Riparian reserve, etc.		
90	ENTRY_USERID	NOT NULL	VARCHAR2(30)
	The USERID of the individual who entered the information.		
95	GEOMETRY	NULL	
	The GEOMETRY is the Forest Cover geographical representation.		
100	OBJECTID	NOT NULL	NUMBER(10,0)
	System generated value uniquely identifying the Forest Cover Reserve. This column is used by SDE.		

Table: RSLT_FOREST_COVER_SILV_POLY

Description:

Spatial representation of the opening's forest cover attributes. The attributes have been denormalized and are limited to the Silviculture attribution of the Forest Cover Polygon.

Columns:

Seq.	Column	Nulls?	Type
* 10	FOREST_COVER_ID	NOT NULL	NUMBER(10,0)
	The FOREST COVER ID is a system-generated value by RESULTS to uniquely identify forest cover polygon.		
20	STOCKING_STANDARD_UNIT_ID	NULL	NUMBER(10,0)
	The STOCKING STANDARD UNIT ID is a system-generated value by RESULTS to uniquely identify standards units.		
30	OPENING_ID	NOT NULL	NUMBER(10,0)
	The OPENING ID is a system generated value by RESULTS to uniquely identify the opening.		
40	STANDARDS_UNIT_ID	NULL	VARCHAR2(4)
	The STANDARDS UNIT ID (SU) is an assigned unique identifier that represents the standards units. The SU that forest cover polygon is associated with.		
50	SILV_POLYGON_NUMBER	NOT NULL	VARCHAR2(30)
	The SILV POLYGON NUMBER is an assigned unique identifier that represents the forest cover polygon.		
60	SILV_POLYGON_AREA	NOT NULL	NUMBER(7,1)
	The SILV POLYGON AREA is the total area in hectares occupied by each polygon. The sum of all areas for a polygon(s) should not be greater than the opening gross area.		
70	SILV_POLYGON_NET_AREA	NOT NULL	NUMBER(7,1)
	The SILV POLYGON NET AREA is the area in hectares occupied by each polygon. The silviculture polygon net area is the silviculture polygon area minus the sum of all the associated non-mappable areas reported within the forest cover polygon.		
80	SILV_NON_MAPPED_AREA	NOT NULL	NUMBER(7,1)
	The SILV NON MAPPED AREA represents the sum of the total non-mappable area (in hectares) reported within each forest cover polygon.		
90	STOCKING_STATUS_CODE	NULL	VARCHAR2(3)
	The STOCKING STATUS CODE is an indication of growing space occupancy relative to establish standard. Status refers to whether the site has met those standards. Stocking status is most often described as NSR-not satisfactorily restocked, IMM-immature, MAT-mature.		
100	STOCKING_TYPE_CODE	NULL	VARCHAR2(3)
	The STOCKING TYPE CODE is a further classification of stocking status for the polygon. Eg. NAT-natural, PL-planting, etc.		
110	STOCKING_CLASS_CODE	NULL	VARCHAR2(1)
	The STOCKING CLASS CODE represents a numeric code representing a range of stems per hectares. Examples: stocking class 0 is immature; stocking class 1 is mature with 76+ stems/ha > 27.5dbh. *2003/01/10 HS: Add a new column.* *Feb 12 2003 wc Changed from Mandatory to Optional*		
120	SILV_RESERVE_CODE	NULL	VARCHAR2(1)
	The SILV RESERVE CODE identifies the spatial pattern of a reserve of retention area associated with a silvicultural system. Reserves are forest patches or individual trees retained during harvesting, or other forestry operations to provide habitat, scenic, biodiversity, and other values. Examples: R-Riparian Reserve; W-Wildlife Tree Patch Reserve; etc.		
130	SILV_RESERVE_OBJECTIVE_CODE	NULL	VARCHAR2(3)
	The SILV RESERVE OBJECTIVE CODE refers to the management goal of the reserve. Examples: WTR-Wildlife Tree Retention; RMA-Riparian reserve, etc.		
140	TREE_COVER_PATTERN_CODE	NULL	VARCHAR2(1)
	The TREE COVER PATTERN CODE is the spatial arrangement of residual patches of overstorey (Layer 1). Applies to polygons in which trees are retained as apart of the silvicultural system or disturbance characteristic (eg. stands with overstorey). Examples: 9-Continuous occurrence with very few inclusions.; 8-Continuous occurrence with several inclusions.; etc.		
150	REENTRY_YEAR	NULL	NUMBER(4,0)
	The RE-ENTRY YEAR is the year the next harvest entry is expected to occur in the opening. Applies to partial-cut silvicultural systems. This field is optional.		
160	REFERENCE_YEAR	NOT NULL	NUMBER(4,0)
	REFERENCE YEAR is the year the forest cover polygon data were collected.		

Table: RSLT_FOREST_COVER_SILV_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
170	SITE_INDEX	NULL	NUMBER(5,0)
	The SITE INDEX is a measure of forest land productivity. Enter the projected average height in metres of the leading species of the forest cover silviculture at 50 years after the stands achieves breast height (1.3m).		
180	SITE_INDEX_SOURCE_CODE	NULL	VARCHAR2(1)
	The SITE INDEX SOURCE CODE is a source or origin of the site index. Example: C-site index from site index curve.		
190	BGC_ZONE_CODE	NULL	VARCHAR2(4)
	The BGC ZONE CODE of the Standards Unit, according to the Biogeoclimatic Ecosystem Classification (BEC) system. Eg. IDF; MS; CWH.		
200	BGC_SUBZONE_CODE	NULL	VARCHAR2(3)
	The BGC SUBZONE CODE of the Standards Unit, according to the BEC system. Eg. dk; xc; mk.		
210	BGC_VARIANT	NULL	VARCHAR2(1)
	The BGC VARIANT according to the BEC system. Eg. 1, 2. A division of the BGC Subzone on the basis of differences in floristic composition of the zonal ecosystem, but usually on the basis of differences in the cover and vigour of the plant species.		
220	BGC_PHASE	NULL	VARCHAR2(1)
	The BGC PHASE according to the BEC system. Accommodates the variation, resulting from local relief, in the regional climate of the subzones and variants.		
230	BEC_SITE_SERIES	NULL	VARCHAR2(4)
	Site series for the given biogeoclimatic unit, according to the BEC system. Eg. 01, 04, 05. Site series is the consideration of all ecosystems capable of producing vegetation belonging to the same plant association at climax.		
240	BEC_SITE_TYPE	NULL	VARCHAR2(3)
	The BEC SITE TYPE for certain site series, according to the BEC system. Site type is the partitionment of the site series according to one or more critical site factors thought to affect ecosystem response to management treatments. Eg. MS, NP.		
250	BEC_SERAL	NULL	VARCHAR2(4)
	The BEC SERAL is the seral (often termed successional) classification in BEC is an integration of site and vegetation classifications with structural stage development. Eg. Accp, Acho.		
260	IS_SILV_IMPLIED_IND	NULL	VARCHAR2(1)
	The IS SILV IMPLIED is the information copied from silviculture component for silviculture component when no separate silviculture information is provided. No significant difference in densities and species composition.		
270	FOREST_COVER_SILV_TYPE	NULL	VARCHAR2(7)
	The FOREST COVER SILV TYPE describes the forest cover stand type characteristics: EVEN, UNEVEN, NONE and UNKNOWN.		
280	S_FOREST_COVER_LAYER_ID	NULL	NUMBER(10,0)
	The S FOREST COVER LAYER ID is a RESULTS system-generated unique identifier for the layer information.		
290	S_TOTAL_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S TOTAL STEMS PER HA is the total stems per hectare for the "even-aged" forest cover polygon.		
300	S_TOTAL_WELL_SPACED_STEMS_HA	NULL	NUMBER(10,0)
	The S TOTAL WELL SPACED STEMS HA is the total number of well-spaced stems per hectare for the "even-aged" forest cover polygon. Stems density for silviculture layer disregarding the M-value.		
310	S_WELL_SPACED_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S WELL SPACED STEMS PER HA is the number of well-spaced stems per hectare for "even-aged" forest cover polygon. Trees are healthy, preferred or acceptable species and well -spaced using the minimum inter-tree distance in the stocking standards (as defined by the SU Identifier).		
320	S_FREE_GROWING_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S FREE GROWING STEMS PER HA is the number of free-growing stems per hectare for "even-aged" forest cover polygon. Free growing stem density for the silviculture (based on the M-value). Free growing trees are healthy, preferred, or acceptable species, well-spaced, free from inhibiting brush, and meet or exceed the minimum height (if applicable).		
330	S_CROWN_CLOSURE_PERCENT	NULL	NUMBER(3,0)
	The S CROWN CLOSURE PERCENT represents the closing together of the crowns of trees in a forest as they age and grow effectively blocking sunlight from reaching the forest floor for "even-aged" forest cover		

Table: RSLT_FOREST_COVER_SILV_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	polygon.		
340	S_BASAL_AREA	NULL	NUMBER(5,0)
	The S BASAL AREA is the cumulative cross-sectional residual basal area (in hectares) of all stems >12.5cm dbh for "even-aged" forest cover polygon. Required if basal area is a part of stocking standard.		
360	S_SPECIES_CODE_1	NULL	VARCHAR2(8)
	The S SPECIES CODE 1 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "even-aged" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
370	S_SPECIES_PERCENT_1	NULL	NUMBER(3,0)
	The S SPECIES PERCENT 1is the estimate of given inventory "even-aged" component tree species percentage within the forest cover polygon.		
380	S_SPECIES_AGE_1	NULL	NUMBER(5,0)
	The S SPECIES AGE 1 is the average age of the given silviculture "even-aged" component tree species percent within the forest cover polygon		
390	S_SPECIES_HEIGHT_1	NULL	NUMBER(3,1)
	The S SPECIES HEIGHT 1 is the average height of the given silviculture "even-aged" component leading tree species in metres.		
400	S_SPECIES_CODE_2	NULL	VARCHAR2(8)
	The S SPECIES CODE 2 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "even-aged" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
410	S_SPECIES_PERCENT_2	NULL	NUMBER(3,0)
	The S SPECIES PERCENT 2 is the estimate of given silviculture "even-aged" component tree species percentage within the forest cover polygon.		
420	S_SPECIES_AGE_2	NULL	NUMBER(5,0)
	The SPECIES AGE 2 is the average age of the given silviculture "even-aged" component tree species percent within the forest cover polygon		
430	S_SPECIES_HEIGHT_2	NULL	NUMBER(3,1)
	The S SPECIES HEIGHT 2 is the average height of the given silviculture "even-aged" component leading tree species in metres.		
440	S_SPECIES_CODE_3	NULL	VARCHAR2(8)
	The S SPECIES CODE 3 is the tree Species Code representing the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "even-aged" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
450	S_SPECIES_PERCENT_3	NULL	NUMBER(3,0)
	The S SPECIES PERCENT 3 is the estimate of given silviculture "even-aged" component tree species percentage within the forest cover polygon.		
460	S_SPECIES_CODE_4	NULL	VARCHAR2(8)
	The S SPECIES CODE 4 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "even-aged" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
470	S_SPECIES_PERCENT_4	NULL	NUMBER(3,0)
	The S SPECIES PERCENT 4 is the estimate of given silviculture "even-aged" component tree species percentage within the forest cover polygon.		
480	S_SPECIES_CODE_5	NULL	VARCHAR2(8)
	The S SPECIES CODE 5 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "even-aged" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
490	S_SPECIES_PERCENT_5	NULL	NUMBER(3,0)
	The S SPECIES PERCENT 5 is the estimate of given silviculture "even-aged" component tree species percentage within the forest cover polygon.		
500	S_MORE_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	The S MORE SPECIES EXIST IND is 'Y' when this layer contains more than 5 species records; these records are available in RSLT FOREST COVER SPECIES.		
510	S_SILV_LABEL	NULL	VARCHAR2(160)
	The S INV LABEL is the silviculture Label for "even-aged" forest cover polygon		
520	S1_FOREST_COVER_LAYER_ID	NULL	NUMBER(10,0)

Table: RSLT_FOREST_COVER_SILV_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	The S1 FOREST COVER LAYER is a RESULTS system-generated unique identifier for the layer information.		
530	S1_TOTAL_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S1 TOTAL STEMS PER HA is the stems per hectare for the "uneven-aged Layer 2-Pole" forest cover polygon.		
540	S1_TOTAL_WELL_SPACED_STEMS_HA	NULL	NUMBER(10,0)
	The S1 TOTAL WELL SPACED STEMS HA is the total number of well-spaced stems per hectare for the "uneven-aged Layer 1-Mature" forest cover polygon. Stems density for silviculture layer disregarding the M-value.		
550	S1_WELL_SPACED_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S1 WELL SPACED STEMS PER HA is the number of well-spaced stems per hectare for "uneven-aged Layer 1-Mature" forest cover polygon. Trees are healthy, preferred or acceptable species and well - spaced using the minimum inter-tree distance in the stocking standards (as defined by the SU Identifier).		
560	S1_FREE_GROWING_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S1 FREE GROWING STEMS PER HA is the number of free-growing stems per hectare for "uneven-aged Layer 1-Mature" forest cover polygon. Free growing stem density for the silviculture (based on the M-value). Free growing trees are healthy, preferred, or acceptable species, well-spaced, free from inhibiting brush, and meet or exceed the minimum height (if applicable).		
570	S1_CROWN_CLOSURE_PERCENT	NULL	NUMBER(3,0)
	The S1 CROWN CLOSURE PERCENT represents the closing together of the crowns of trees in a forest as they age and grow effectively blocking sunlight from reaching the forest floor for "uneven-aged Layer 1-Mature" forest cover polygon.		
580	S1_BASAL_AREA	NULL	NUMBER(5,0)
	The S1 BASAL AREA is the cumulative cross-sectional residual basal area (in hectares) of all stems >12.5cm dbh for "uneven-aged Layer 1-Mature" forest cover polygon. Required if basal area is a part of stocking standard. *asdf*		
600	S1_SPECIES_CODE_1	NULL	VARCHAR2(8)
	The S1 SPECIES CODE 1 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 1-Mature" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
610	S1_SPECIES_PERCENT_1	NULL	NUMBER(3,0)
	The S1 SPECIES PERCENT 1 is the estimate of given silviculture "uneven-aged Layer 1-Mature" component tree species percentage within the forest cover polygon.		
620	S1_SPECIES_AGE_1	NULL	NUMBER(5,0)
	The S1 SPECIES PERCENT 1 of the given silviculture "uneven-aged Layer 1-Mature" component tree species percent within the forest cover polygon		
630	S1_SPECIES_HEIGHT_1	NULL	NUMBER(3,1)
	The S1 SPECIES HEIGHT 1is the average height of the given silviculture "uneven-aged Layer 1-Mature" component leading tree species in metres.		
640	S1_SPECIES_CODE_2	NULL	VARCHAR2(8)
	The S1 SPECIES CODE 2 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 1-Mature" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
650	S1_SPECIES_PERCENT_2	NULL	NUMBER(3,0)
	The S1 SPECIES PERCENT 2 is the estimate of given silviculture "uneven-aged Layer 1-Mature" component tree species percentage within the forest cover polygon.		
660	S1_SPECIES_AGE_2	NULL	NUMBER(5,0)
	The S1 SPECIES AGE 2 is the average age of the given silviculture "uneven-aged Layer 1-Mature" component tree species percent within the forest cover polygon		
670	S1_SPECIES_HEIGHT_2	NULL	NUMBER(3,1)
	The S1 SPECIES HEIGHT 2 is the average height of the given silviculture "uneven-aged Layer 1-Mature" component leading tree species in metres.		
680	S1_SPECIES_CODE_3	NULL	VARCHAR2(8)
	The S1 SPECIES CODE 3 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 1-Mature" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		

Table: RSLT_FOREST_COVER_SILV_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
690	S1_SPECIES_PERCENT_3	NULL	NUMBER(3,0)
	The S1 SPECIES PERCENT 3 is the estimate of given silviculture "uneven-aged Layer 1-Mature" component tree species percentage within the forest cover polygon.		
700	S1_SPECIES_CODE_4	NULL	VARCHAR2(8)
	The S1 SPECIES CODE 4 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 1-Mature" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
710	S1_SPECIES_PERCENT_4	NULL	NUMBER(3,0)
	The S1 SPECIES PERCENT 4 is the estimate of given silviculture "uneven-aged Layer 1-Mature" component tree species percentage within the forest cover polygon.		
720	S1_SPECIES_CODE_5	NULL	VARCHAR2(8)
	The S1 SPECIES CODE 5 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 1-Mature" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
730	S1_SPECIES_PERCENT_5	NULL	NUMBER(3,0)
	The S1 SPECIES PERCENT 5 is the estimate of given silviculture "uneven-aged Layer 1-Mature" component tree species percentage within the forest cover polygon.		
740	S1_MORE_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	The S1 MORE SPECIES EXIST IND is 'Y' when this layer contains more than 5 species records; these records are available in RSLT FOREST COVER SPECIES.		
750	S1_SILV_LABEL	NULL	VARCHAR2(160)
	The S1 SILV LABEL is the silviculture Label for "uneven-aged Layer 1-Mature" forest cover polygon		
760	S2_FOREST_COVER_LAYER_ID	NULL	NUMBER(10,0)
	The S2 FOREST COVER LAYER ID is a RESULTS system-generated unique identifier for the layer information.		
770	S2_TOTAL_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S2 TOTAL STEMS PER HA is the total stems per hectare for the "uneven-aged Layer 2-Pole" forest cover polygon.		
780	S2_TOTAL_WELL_SPACED_STEMS_HA	NULL	NUMBER(10,0)
	The S2 TOTAL WELL SPACED STEMS HA is the total number of well-spaced stems per hectare for the "uneven-aged Layer 2-Pole" forest cover polygon. Stems density for silviculture layer disregarding the M-value.		
790	S2_WELL_SPACED_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S2 TOTAL WELL SPACED STEMS HA is the number of well-spaced stems per hectare for "uneven-aged Layer 2-Pole" forest cover polygon. Trees are healthy, preferred or acceptable species and well - spaced using the minimum inter-tree distance in the stocking standards (as defined by the SU Identifier).		
800	S2_FREE_GROWING_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S2 FREE GROWING STEMS PER HA is the number of free-growing stems per hectare for "uneven-aged Layer 2-Pole" forest cover polygon. Free growing stem density for the silviculture (based on the M-value). Free growing trees are healthy, preferred, or acceptable species, well-spaced, free from inhibiting brush, and meet or exceed the minimum height (if applicable).		
810	S2_CROWN_CLOSURE_PERCENT	NULL	NUMBER(3,0)
	The S2 CROWN CLOSURE PERCENT represents the closing together of the crowns of trees in a forest as they age and grow effectively blocking sunlight from reaching the forest floor for "uneven-aged Layer 2-Pole" forest cover polygon.		
820	S2_BASAL_AREA	NULL	NUMBER(5,0)
	The S2 BASAL AREA is the cumulative cross-sectional residual basal area (in hectares) of all stems >12.5cm dbh for "uneven-aged Layer 2-Pole" forest cover polygon. Required if basal area is a part of stocking standard.		
840	S2_SPECIES_CODE_1	NULL	VARCHAR2(8)
	The S2 SPECIES CODE 1 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 2-Pole" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
850	S2_SPECIES_PERCENT_1	NULL	NUMBER(3,0)
	The S2 SPECIES PERCENT 1is the estimate of given silviculture "uneven-aged Layer 2-Pole" component tree species percentage within the forest cover polygon.		
860	S2_SPECIES_AGE_1	NULL	NUMBER(5,0)

Table: RSLT_FOREST_COVER_SILV_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	The S2 SPECIES AGE 1 is the average age of the given silviculture "uneven-aged Layer 2-Pole" component tree species percent within the forest cover polygon		
870	S2_SPECIES_HEIGHT_1	NULL	NUMBER(3,1)
	The S2 SPECIES HEIGHT 1 is the average height of the given silviculture "uneven-aged Layer 2-Pole" component leading tree species in metres.		
880	S2_SPECIES_CODE_2	NULL	VARCHAR2(8)
	The S2 SPECIES CODE 2 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 2-Pole" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
890	S2_SPECIES_PERCENT_2	NULL	NUMBER(3,0)
	The S2 SPECIES PERCENT 2 is the estimate of given silviculture "uneven-aged Layer 2-Pole" component tree species percentage within the forest cover polygon.		
900	S2_SPECIES_AGE_2	NULL	NUMBER(5,0)
	The S2 SPECIES AGE 2 is the average age of the given silviculture "uneven-aged Layer 2-Pole" component tree species percent within the forest cover polygon		
910	S2_SPECIES_HEIGHT_2	NULL	NUMBER(3,1)
	The S2 SPECIES HEIGHT 2 is the average height of the given silviculture "uneven-aged Layer 2-Pole" component leading tree species in metres.		
920	S2_SPECIES_CODE_3	NULL	VARCHAR2(8)
	The S2 SPECIES CODE 3 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 2-Pole" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
930	S2_SPECIES_PERCENT_3	NULL	NUMBER(3,0)
	The S2 SPECIES PERCENT 3 is the estimate of given silviculture "uneven-aged Layer 2-Pole" component tree species percentage within the forest cover polygon.		
940	S2_SPECIES_CODE_4	NULL	VARCHAR2(8)
	The S2 SPECIES CODE 4 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 2-Pole" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
950	S2_SPECIES_PERCENT_4	NULL	NUMBER(3,0)
	The S2 SPECIES PERCENT 4 is the estimate of given silviculture "uneven-aged Layer 2-Pole" component tree species percentage within the forest cover polygon.		
960	S2_SPECIES_CODE_5	NULL	VARCHAR2(8)
	The S2 SPECIES CODE 5 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 2-Pole" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
970	S2_SPECIES_PERCENT_5	NULL	NUMBER(3,0)
	The S2 SPECIES PERCENT 5 is the estimate of given silviculture "uneven-aged Layer 2-Pole" component tree species percentage within the forest cover polygon.		
980	S2_MORE_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	The S2 MORE SPECIES EXIST IND is 'Y' when this layer contains more than 5 species records; these records are available in RSLT FOREST COVER SPECIES.		
990	S2_SILV_LABEL	NULL	VARCHAR2(160)
	The S2 SILV LABEL is the silviculture Label for "uneven-aged Layer 2-Pole" forest cover polygon		
1000	S3_FOREST_COVER_LAYER_ID	NULL	NUMBER(10,0)
	The S3 FOREST COVER LABEL ID is a RESULTS system-generated unique identifier for the layer information.		
1010	S3_TOTAL_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S3 TOTAL STEMS PER HA is the total stems per hectare for the "uneven-aged Layer 3-Sapling" forest cover polygon.		
1020	S3_TOTAL_WELL_SPACED_STEMS_HA	NULL	NUMBER(10,0)
	The S3 TOTAL WELL SPACED STEMS HA is the total number of well-spaced stems per hectare for the "uneven-aged Layer 3-Sapling" forest cover polygon. Stems density for silviculture layer disregarding the M-value.		
1030	S3_WELL_SPACED_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S3 WELL SPACED STEMS PER HA is the number of well-spaced stems per hectare for "uneven-aged Layer 3-Sapling" forest cover polygon. Trees are healthy, preferred or acceptable species and well -		

Table: RSLT_FOREST_COVER_SILV_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	spaced using the minimum inter-tree distance in the stocking standards (as defined by the SU Identifier).		
1040	S3_FREE_GROWING_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S3 FREE GROWING STEMS PER HA is the number of free-growing stems per hectare for "uneven-aged Layer 3-Sapling" forest cover polygon. Free growing stem density for the silviculture (based on the M-value). Free growing trees are healthy, preferred, or acceptable species, well-spaced, free from inhibiting brush, and meet or exceed the minimum height (if applicable).		
1050	S3_CROWN_CLOSURE_PERCENT	NULL	NUMBER(3,0)
	The S3 CROWN CLOSURE PERCENT represents the closing together of the crowns of trees in a forest as they age and grow effectively blocking sunlight from reaching the forest floor for "uneven-aged Layer 3-Sapling" forest cover polygon.		
1060	S3_BASAL_AREA	NULL	NUMBER(5,0)
	The S3 BASAL AREA is the cumulative cross-sectional residual basal area (in hectares) of all stems >12.5cm dbh for "uneven-aged Layer 3-Sapling" forest cover polygon. Required if basal area is a part of stocking standard.		
1070	S3_SPECIES_CODE_1	NULL	VARCHAR2(8)
	The S3 SPECIES CODE 1 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 3-Sapling" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
1075	S3_SPECIES_PERCENT_1	NULL	NUMBER(3,0)
	The S3 SPECIES PERCENT 1 is the estimate of given silviculture "uneven-aged Layer 3-Sapling" component tree species percentage within the forest cover polygon.		
1080	S3_SPECIES_AGE_1	NULL	NUMBER(5,0)
	The S3 SPECIES AGE 1 is the average age of the given silviculture "uneven-aged Layer 3-Sapling" component tree species percent within the forest cover polygon		
1085	S3_SPECIES_HEIGHT_1	NULL	NUMBER(3,1)
	The S3 SPECIES HEIGHT 1 is the average height of the given silviculture "uneven-aged Layer 3-Sapling" component leading tree species in metres.		
1090	S3_SPECIES_CODE_2	NULL	VARCHAR2(8)
	The S3 SPECIES CODE 2 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 3-Sapling" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
1095	S3_SPECIES_PERCENT_2	NULL	NUMBER(3,0)
	The S3 SPECIES PERCENT 2 is the estimate of given silviculture "uneven-aged Layer 3-Sapling" component tree species percentage within the forest cover polygon.		
1100	S3_SPECIES_AGE_2	NULL	NUMBER(5,0)
	The S3 SPECIES AGE 2 is the average age of the given silviculture "uneven-aged Layer 3-Sapling" component tree species percent within the forest cover polygon		
1110	S3_SPECIES_HEIGHT_2	NULL	NUMBER(3,1)
	The S3 SPECIES HEIGHT 2 is the average height of the given silviculture "uneven-aged Layer 3-Sapling" component leading tree species in metres.		
1120	S3_SPECIES_CODE_3	NULL	VARCHAR2(8)
	The S3 SPECIES CODE 3 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 3-Sapling" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
1130	S3_SPECIES_PERCENT_3	NULL	NUMBER(3,0)
	The S3 SPECIES PERCENT 3 is the estimate of given silviculture "uneven-aged Layer 3-Sapling" component tree species percentage within the forest cover polygon.		
1140	S3_SPECIES_CODE_4	NULL	VARCHAR2(8)
	The S3 SPECIES CODE 4 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 3-Sapling" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
1150	S3_SPECIES_PERCENT_4	NULL	NUMBER(3,0)
	The S3 SPECIES PERCENT 4 is the estimate of given silviculture "uneven-aged Layer 3-Sapling" component tree species percentage within the forest cover polygon.		
1160	S3_SPECIES_CODE_5	NULL	VARCHAR2(8)
	The S3 SPECIES CODE 5 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 3-Sapling" component. Example: CW-WESTERN		

Table: RSLT_FOREST_COVER_SILV_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	RED CEDAR;SW-WHITE SPRUCE; etc.		
1170	S3_SPECIES_PERCENT_5	NULL	NUMBER(3,0)
	The S3 SPECIES PERCENT 5 is the estimate of given silviculture "uneven-aged Layer 3-Sapling" component tree species percentage within the forest cover polygon.		
1180	S3_MORE_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	The S3 MORE SPECIES EXIST IND is 'Y' when this layer contains more than 5 species records; these records are available in RSLT FOREST COVER SPECIES.		
1190	S3_SILV_LABEL	NULL	VARCHAR2(160)
	The S3 SILV LABEL is the silviculture Label for "uneven-aged Layer 3-Sapling" forest cover polygon		
1200	S4_FOREST_COVER_LAYER_ID	NULL	NUMBER(10,0)
	The S4 FOREST COVER LAYER ID is a RESULTS system-generated unique identifier for the layer information.		
1210	S4_TOTAL_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S4 TOTAL STEMS PER HA is the total stems per hectare for the "uneven-aged Layer 4-Regen" forest cover polygon.		
1220	S4_TOTAL_WELL_SPACED_STEMS_HA	NULL	NUMBER(10,0)
	The S4 TOTAL WELL SPACED STEMS HA is the total number of well-spaced stems per hectare for the "uneven-aged Layer 4-Regen" forest cover polygon. Stems density for silviculture layer disregarding the M-value.		
1230	S4_WELL_SPACED_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S4 WELL SPACED STEMS PER HA is the number of well-spaced stems per hectare for "uneven-aged Layer 4-Regen" forest cover polygon. Trees are healthy, preferred or acceptable species and well - spaced using the minimum inter-tree distance in the stocking standards (as defined by the SU Identifier).		
1240	S4_FREE_GROWING_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S4 FREE GROWING STEMS PER HA is the number of free-growing stems per hectare for "uneven-aged Layer 4-Regen" forest cover polygon. Free growing stem density for the silviculture (based on the M-value). Free growing trees are healthy, preferred, or acceptable species, well-spaced, free from inhibiting brush, and meet or exceed the minimum height (if applicable).		
1250	S4_CROWN_CLOSURE_PERCENT	NULL	NUMBER(3,0)
	The S4 CROWN CLOSURE PERCENT represents the closing together of the crowns of trees in a forest as they age and grow effectively blocking sunlight from reaching the forest floor for "uneven-aged Layer 4-Regen" forest cover polygon.		
1260	S4_BASAL_AREA	NULL	NUMBER(5,0)
	The S4 BASAL AREA is the cumulative cross-sectional residual basal area (in hectares) of all stems >12.5cm dbh for "uneven-aged Layer 4-Regen" forest cover polygon. Required if basal area is a part of stocking standard.		
1280	S4_SPECIES_CODE_1	NULL	VARCHAR2(8)
	The S4 SPECIES PERCENT 1 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 4-Regen" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
1290	S4_SPECIES_PERCENT_1	NULL	NUMBER(3,0)
	The S4 SPECIES PERCENT 1 is the estimate of given silviculture "uneven-aged Layer 4-Regen" component tree species percentage within the forest cover polygon.		
1300	S4_SPECIES_AGE_1	NULL	NUMBER(5,0)
	The S4 SPECIES AGE 1 is the average age of the given silviculture "uneven-aged Layer 4-Regen" component tree species percent within the forest cover polygon.		
1310	S4_SPECIES_HEIGHT_1	NULL	NUMBER(3,1)
	The S4 SPECIES HEIGHT 1 is the average height of the given silviculture "uneven-aged Layer 4-Regen" component leading tree species in metres.		
1320	S4_SPECIES_CODE_2	NULL	VARCHAR2(8)
	The S4 SPECIES CODE represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 4-Regen" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
1330	S4_SPECIES_PERCENT_2	NULL	NUMBER(3,0)
	The S4 SPECIES PERCENT 2 is the estimate of given silviculture "uneven-aged Layer 4-Regen" component tree species percentage within the forest cover polygon.		
1340	S4_SPECIES_AGE_2	NULL	NUMBER(5,0)

Table: RSLT_FOREST_COVER_SILV_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	The S4 SPECIES AGE 2 is the average age of the given silviculture "uneven-aged Layer 4-Regen" component tree species percent within the forest cover polygon		
1350	S4_SPECIES_HEIGHT_2	NULL	NUMBER(3,1)
	The S4 SPECIES HEIGHT 2 is the average height of the given silviculture "uneven-aged Layer 4-Regen" component leading tree species in metres.		
1360	S4_SPECIES_CODE_3	NULL	VARCHAR2(8)
	The S4 SPECIES CODE 3 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 4-Regen" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
1370	S4_SPECIES_PERCENT_3	NULL	NUMBER(3,0)
	The S4 SPECIES PERCENT 3 is the estimate of given silviculture "uneven-aged Layer 4-Regen" component tree species percentage within the forest cover polygon.		
1380	S4_SPECIES_CODE_4	NULL	VARCHAR2(8)
	The S4 SPECIES PERCENT 4 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 4-Regen" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
1390	S4_SPECIES_PERCENT_4	NULL	NUMBER(3,0)
	The S4 SPECIES PERCENT 4 is the estimate of given silviculture "uneven-aged Layer 4-Regen" component tree species percentage within the forest cover polygon.		
1400	S4_SPECIES_CODE_5	NULL	VARCHAR2(8)
	The S4 SPECIES CODE 5 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 4-Regen" component. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
1410	S4_SPECIES_PERCENT_5	NULL	NUMBER(3,0)
	The S4 SPECIES PERCENT 5 is the estimate of given silviculture "uneven-aged Layer 4-Regen" component tree species percentage within the forest cover polygon.		
1420	S4_MORE_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	The S4 MORE SPECIES EXIST IND is 'Y' when this layer contains more than 5 species records; these records are available in RSLT FOREST COVER SPECIES.		
1430	S4_SILV_LABEL	NULL	VARCHAR2(160)
	The S4 SILV LABEL is the Silviculture Label for "uneven-aged Layer 4-Regen" forest cover polygon		
1440	GEOMETRY_EXIST_IND	NULL	VARCHAR2(1)
	The GEOMETRY EXIST IND indicates if there is geometry for the opening. A value of 'Y' indicates there is geometry. A value of 'N' indicates there is no geometry.		
1450	FEATURE_AREA	NULL	NUMBER(11,4)
	The FEATURE AREA is the area of the feature in square meters.		
1460	FEATURE_PERIMETER	NULL	NUMBER(11,4)
	The FEATURE PERIMETER is the perimeter of the feature in meters.		
1470	CAPTURE_METHOD_CODE	NULL	VARCHAR2(30)
	The CAPTURE METHOD CODE is a code defining the capture method. (e.g. digitize).		
1480	DATA_SOURCE_CODE	NULL	VARCHAR2(10)
	The DATA SOURCE CODE is a code defining the source of the spatial feature (e.g. GPS, TRIM).		
1490	OBSERVATION_DATE	NULL	DATE
	The OBSERVATION DATE is the geometry collection date.		
1500	DATA_QUALITY_COMMENT	NULL	VARCHAR(255)
	The DATA QUALITY COMMENT is a comment indicating the Geometry accuracy.		
1510	FOREST_COVER_WHO_CREATED	NOT NULL	VARCHAR2(30)
	The FOREST COVER WHO CREATED is the USERID of the individual who created the activity record.		
1520	FOREST_COVER_WHEN_CREATED	NOT NULL	DATE
	The FOREST COVER WHO UPDATED is the date and time when the activity record was created.		
1530	FOREST_COVER_WHO_UPDATED	NOT NULL	VARCHAR2(30)
	The FOREST COVER WHEN UPDATED is the USERID of the individual who last updated the activity record.		
1540	FOREST_COVER_WHEN_UPDATED	NOT NULL	DATE
	THE FOREST COVER WHEN UPDATED is the date and time when the activity record was last updated.		
1550	CHANGE_TIMESTAMP1	NOT NULL	DATE
	The date and time of the last update to the FOREST COVER table.		

Table: RSLT_FOREST_COVER_SILV_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
1560	CHANGE_TIMESTAMP2	NULL	DATE
	The date and time of the last update to the STOCKING STANDARD UNIT table.		
1570	CHANGE_TIMESTAMP3	NULL	DATE
	The date and time of the last update to the FOREST COVER GEOMETRY table.		
1580	CHANGE_TIMESTAMP4	NULL	DATE
	The date and time of the last update to the FOREST COVER LAYER table.		
1590	CHANGE_TIMESTAMP5	NULL	DATE
	The date and time of the last update to the FOREST COVER SPECIES table.		
1600	CHANGE_COUNT1	NULL	NUMBER(2)
	A count of all of the FOREST COVER LAYER records that relate to this record.		
1610	CHANGE_COUNT2	NULL	NUMBER(2)
	A count of all of the FOREST COVER SPECIES records that relate to this record.		
1620	FEATURE_CLASS_SKEY	NULL	NUMBER(10,0)
	The FEATURE CLASS SKEY is the unique key assigned to a Feature Class by the Ministry of Forests.		
1630	GEOMETRY	NULL	
	The GEOMETRY is the Forest Cover geographical representation.		
1640	OBJECTID	NOT NULL	INTEGER
	The OBJECTID is a system generated value uniquely identifying the opening. Used by SDE.		

Unique Constraints:

RSLT_FCS_UK
OBJECTID

Foreign Keys:

RSLT_FCS_RSLT_OPEN_FK
OPENING_ID = RSLT_OPENING_POLYGON.OPENING_ID
RSLT_FCS_RSLT_SU_FK
STOCKING_STANDARD_UNIT_ID = RSLT_STANDARDS_UNIT_POLY.STOCKING_STANDARD_UNIT_ID

Indexes:

RSLT_FCS_GEOM_I
GEOMETRY
RSLT_FCS_RSLT_OPEN_FK_I
OPENING_ID
RSLT_FCS_RSLT_SU_FK_I
STOCKING_STANDARD_UNIT_ID

Table: RSLT_FOREST_COVER_SILV_SVW

Description:

Spatial representation of the opening's forest cover attributes. The attributes have been denormalized and are limited to the Silviculture attribution of the Forest Cover Polygon.

Columns:

Seq.	Column	Nulls?	Type
10	FOREST_COVER_ID	NOT NULL	NUMBER(10,0)
	The FOREST COVER ID is a system-generated value by RESULTS to uniquely identify forest cover polygon.		
20	STOCKING_STANDARD_UNIT_ID	NULL	NUMBER(10,0)
	The STOCKING STANDARD UNIT ID is a system-generated value by RESULTS to uniquely identify standards units.		
30	OPENING_ID	NOT NULL	NUMBER(10,0)
	The OPENING ID is a system generated value by RESULTS to uniquely identify the opening.		
40	STANDARDS_UNIT_ID	NULL	VARCHAR2(4)
	The STANDARDS UNIT ID (SU) is an assigned unique identifier that represents the standards units. The SU that forest cover polygon is associated with.		
50	SILV_POLYGON_NUMBER	NULL	VARCHAR2(30)
	The SILV POLYGON NUMBER is an assigned unique identifier that represents the forest cover polygon.		
60	SILV_POLYGON_AREA	NULL	NUMBER(7,1)
	The SILV POLYGON AREA is the total area in hectares occupied by each polygon. The sum of all areas for a polygon(s) should not be greater than the opening gross area.		
70	SILV_POLYGON_NET_AREA	NULL	NUMBER(7,1)
	The SILV POLYGON NET AREA is the area in hectares occupied by each polygon. The silviculture polygon net area is the silviculture polygon area minus the sum of all the associated non-mappable areas reported within the forest cover polygon.		
80	SILV_NON_MAPPED_AREA	NULL	NUMBER(7,1)
	The SILV NON MAPPED AREA represents the sum of the total non-mappable area reported within each forest cover polygon.		
90	STOCKING_STATUS_CODE	NULL	VARCHAR2(3)
	The STOCKING STATUS CODE is an indication of growing space occupancy relative to establish standard. Status refers to whether the site has met those standards. Stocking status is most often described as NSR-not satisfactorily restocked, IMM-immature, MAT-mature.		
100	STOCKING_TYPE_CODE	NULL	VARCHAR2(3)
	The STOCKING TYPE CODE is a further classification of stocking status for the polygon. Eg. NAT-natural, PL-planting, etc.		
110	STOCKING_CLASS_CODE	NULL	VARCHAR2(1)
	The STOCKING CLASS CODE represents a numeric code representing a range of stems per hectares. Examples: stocking class 0 is immature; stocking class 1 is mature with 76+ stems/ha > 27.5dbh.		
120	SILV_RESERVE_CODE	NULL	VARCHAR2(1)
	The SILV RESERVE CODE identifies the spatial pattern of a reserve of retention area associated with a silvicultural system. Reserves are forest patches or individual trees retained during harvesting, or other forestry operations to provide habitat, scenic, biodiversity, and other values.		
130	SILV_RESERVE_OBJECTIVE_CODE	NULL	VARCHAR2(3)
	The SILV RESERVE OBJECTIVE CODE refers to the management goal of the reserve. Examples: WTR-Wildlife Tree Retention; RMA-Riparian reserve, etc.		
140	TREE_COVER_PATTERN_CODE	NULL	VARCHAR2(1)
	The TREE COVER PATTERN CODE is the spatial arrangement of residual patches of overstorey (Layer 1). Applies to polygons in which trees are retained as apart of the silvicultural system or disturbance characteristic (eg. stands with overstorey).		
150	REENTRY_YEAR	NULL	NUMBER(4,0)
	The RE-ENTRY YEAR is the year the next harvest entry is expected to occur in the opening. Applies to partial-cut silvicultural systems. This field is optional.		
160	REFERENCE_YEAR	NULL	NUMBER(4,0)
	REFERENCE YEAR is the year the forest cover polygon data were collected.		
170	SITE_INDEX	NULL	NUMBER(5,0)
	The SITE INDEX is a measure of forest land productivity. Enter the projected average height in metres of the leading species of the forest cover silviculture at 50 years after the stands achieves breast height (1.3m).		

Table: RSLT_FOREST_COVER_SILV_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
180	SITE_INDEX_SOURCE_CODE	NULL	VARCHAR2(1)
	The SITE INDEX SOURCE CODE is a source or origin of the site index. Example: C-site index from site index curve.		
190	BGC_ZONE_CODE	NULL	VARCHAR2(4)
	The BGC ZONE CODE of the SU, according to the Biogeoclimatic Ecosystem Classification (BEC) system. Eg. IDF; MS; CWH.		
200	BGC_SUBZONE_CODE	NULL	VARCHAR2(3)
	The BGC SUBZONE CODE of the SU, according to the BEC system. Eg. dk; xc; mk.		
210	BGC_VARIANT	NULL	VARCHAR2(1)
	The BGC VARIANT according to the BEC system. Eg. 1, 2. A division of the BGC Subzone on the basis of differences in floristic composition of the zonal ecosystem, but usually on the basis of differences in the cover and vigour of the plant species.		
220	BGC_PHASE	NULL	VARCHAR2(1)
	The BGC PHASE according to the BEC system. Accommodates the variation, resulting from local relief, in the regional climate of the subzones and variants.		
230	BEC_SITE_SERIES	NULL	VARCHAR2(4)
	Site series for the given biogeoclimatic unit, according to the BEC system. Eg. 01, 04, 05. Site series is the consideration of all ecosystems capable of producing vegetation belonging to the same plant association at climax.		
240	BEC_SITE_TYPE	NULL	VARCHAR2(3)
	The BEC SITE TYPE for certain site series, according to the BEC system. Site type is the partitionment of the site series according to one or more critical site factors thought to affect ecosystem response to management treatments.		
250	BEC_SERAL	NULL	VARCHAR2(4)
	The BEC SERAL is the seral (often termed successional) classification in BEC is an integration of site and vegetation classifications with structural stage development		
260	IS_SILV_IMPLIED_IND	NULL	VARCHAR2(1)
	The IS SILV IMPLIED is the information copied from silviculture component for silviculture component when no separate silviculture information is provided. No significant difference in densities and species composition.		
270	FOREST_COVER_SILV_TYPE	NULL	VARCHAR2(7)
	The FOREST COVER SILV TYPE describes the forest cover stand type characteristics: EVEN, UNEVEN, NONE and UNKNOWN.		
280	S_FOREST_COVER_LAYER_ID	NULL	NUMBER(10,0)
	The S FOREST COVER LAYER ID is a RESULTS system-generated unique identifier for the layer information.		
290	S_TOTAL_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S TOTAL STEMS PER HA is the total stems per hectare for the "even-aged" forest cover polygon.		
300	S_TOTAL_WELL_SPACED_STEMS_HA	NULL	NUMBER(10,0)
	The S TOTAL WELL SPACED STEMS HA is the total number of well-spaced stems per hectare for the "even-aged" forest cover polygon. Stems density for silviculture layer disregarding the M-value.		
310	S_WELL_SPACED_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S WELL SPACED STEMS PER HA is the number of well-spaced stems per hectare for "even-aged" forest cover polygon. Trees are healthy, preferred or acceptable species and well -spaced using the minimum inter-tree distance in the stocking standards (as defined by the SU Identifier).		
320	S_FREE_GROWING_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S FREE GROWING STEMS PER HA is the number of free-growing stems per hectare for "even-aged" forest cover polygon. Free growing stem density for the silviculture (based on the M-value). Free growing trees are healthy, preferred, or acceptable species, well-spaced, free from inhibiting brush, and meet or exceed the minimum height (if applicable).		
330	S_CROWN_CLOSURE_PERCENT	NULL	NUMBER(3,0)
	The S CROWN CLOSURE PERCENT represents the closing together of the crowns of trees in a forest as they age and grow effectively blocking sunlight from reaching the forest floor for "even-aged" forest cover polygon.		
340	S_BASAL_AREA	NULL	NUMBER(5,0)
	The S BASAL AREA is the cumulative cross-sectional residual basal area of all stems >12.5cm dbh for "even-aged" forest cover polygon. Required if basal area is a part of stocking standard.		

Table: RSLT_FOREST_COVER_SILV_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
350	S_SPECIES_CODE_1	NULL	VARCHAR2(8)
	The S SPECIES CODE 1 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "even-aged" component		
360	S_SPECIES_PERCENT_1	NULL	NUMBER(3,0)
	The S SPECIES PERCENT 1 is the estimate of given inventory "even-aged" component tree species percentage within the forest cover polygon.		
370	S_SPECIES_AGE_1	NULL	NUMBER(5,0)
	The S SPECIES AGE 1 is the average age of the given silviculture "even-aged" component tree species percent within the forest cover polygon		
380	S_SPECIES_HEIGHT_1	NULL	NUMBER(3,1)
	The S SPECIES HEIGHT 1 is the average height of the given silviculture "even-aged" component leading tree species in metres.		
390	S_SPECIES_CODE_2	NULL	VARCHAR2(8)
	The S SPECIES CODE 2 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "even-aged" component		
400	S_SPECIES_PERCENT_2	NULL	NUMBER(3,0)
	The S SPECIES PERCENT 2 is the estimate of given silviculture "even-aged" component tree species percentage within the forest cover polygon.		
410	S_SPECIES_AGE_2	NULL	NUMBER(5,0)
	The SPECIES AGE 2 is the average age of the given silviculture "even-aged" component tree species percent within the forest cover polygon		
420	S_SPECIES_HEIGHT_2	NULL	NUMBER(3,1)
	The S SPECIES HEIGHT 2 is the average height of the given silviculture "even-aged" component leading tree species in metres.		
430	S_SPECIES_CODE_3	NULL	VARCHAR2(8)
	The S SPECIES CODE 3 is the tree Species Code representing the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "even-aged" component		
440	S_SPECIES_PERCENT_3	NULL	NUMBER(3,0)
	The S SPECIES PERCENT 3 is the estimate of given silviculture "even-aged" component tree species percentage within the forest cover polygon.		
450	S_SPECIES_CODE_4	NULL	VARCHAR2(8)
	The S SPECIES CODE 4 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "even-aged" component		
460	S_SPECIES_PERCENT_4	NULL	NUMBER(3,0)
	The S SPECIES PERCENT 4 is the estimate of given silviculture "even-aged" component tree species percentage within the forest cover polygon.		
470	S_SPECIES_CODE_5	NULL	VARCHAR2(8)
	The S SPECIES CODE 5 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "even-aged" component		
480	S_SPECIES_PERCENT_5	NULL	NUMBER(3,0)
	The S SPECIES PERCENT 5 is the estimate of given silviculture "even-aged" component tree species percentage within the forest cover polygon.		
490	S_MORE_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	The S MORE SPECIES EXIST IND is 'Y' when this layer contains more than 5 species records; these records are available in RSLT FOREST COVER SPECIES.		
500	S_SILV_LABEL	NULL	VARCHAR2(160)
	The S SILV LABEL is the silviculture Label for "even-aged" forest cover polygon		
510	S1_FOREST_COVER_LAYER_ID	NULL	NUMBER(10,0)
	The S1 FOREST COVER LAYER is a RESULTS system-generated unique identifier for the layer information.		
520	S1_TOTAL_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S1 TOTAL STEMS PER HA is the stems per hectare for the "uneven-aged Layer 2-Pole" forest cover polygon.		
530	S1_TOTAL_WELL_SPACED_STEMS_HA	NULL	NUMBER(10,0)
	The S1 TOTAL WELL SPACED STEMS HA is the total number of well-spaced stems per hectare for the "uneven-aged Layer 1-Mature" forest cover polygon. Stems density for silviculture layer disregarding the M-value.		

Table: RSLT_FOREST_COVER_SILV_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
540	S1_WELL_SPACED_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S1 WELL SPACED STEMS PER HA is the number of well-spaced stems per hectare for "uneven-aged Layer 1-Mature" forest cover polygon. Trees are healthy, preferred or acceptable species and well - spaced using the minimum inter-tree distance in the stocking standards (as defined by the SU Identifier).		
550	S1_FREE_GROWING_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S1 FREE GROWING STEMS PER HA is the number of free-growing stems per hectare for "uneven-aged Layer 1-Mature" forest cover polygon. Free growing stem density for the silviculture (based on the M-value). Free growing trees are healthy, preferred, or acceptable species, well-spaced, free from inhibiting brush, and meet or exceed the minimum height (if applicable).		
560	S1_CROWN_CLOSURE_PERCENT	NULL	NUMBER(3,0)
	The S1 CROWN CLOSURE PERCENT represents the closing together of the crowns of trees in a forest as they age and grow effectively blocking sunlight from reaching the forest floor for "uneven-aged Layer 1-Mature" forest cover polygon.		
570	S1_BASAL_AREA	NULL	NUMBER(5,0)
	The S1 BASAL AREA is the cumulative cross-sectional residual basal area of all stems >12.5cm dbh for "uneven-aged Layer 1-Mature" forest cover polygon. Required if basal area is a part of stocking standard.		
580	S1_SPECIES_CODE_1	NULL	VARCHAR2(8)
	The S1 SPECIES CODE 1 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 1-Mature" component		
590	S1_SPECIES_PERCENT_1	NULL	NUMBER(3,0)
	The S1 SPECIES PERCENT 1 is the estimate of given silviculture "uneven-aged Layer 1-Mature" component tree species percentage within the forest cover polygon.		
600	S1_SPECIES_AGE_1	NULL	NUMBER(5,0)
	The S1 SPECIES AGE 1 of the given silviculture "uneven-aged Layer 1-Mature" component tree species percent within the forest cover polygon		
610	S1_SPECIES_HEIGHT_1	NULL	NUMBER(3,1)
	The S1 SPECIES HEIGHT 1 is the average height of the given silviculture "uneven-aged Layer 1-Mature" component leading tree species in metres.		
620	S1_SPECIES_CODE_2	NULL	VARCHAR2(8)
	The S1 SPECIES CODE 2 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 1-Mature" component		
630	S1_SPECIES_PERCENT_2	NULL	NUMBER(3,0)
	The S1 SPECIES PERCENT 2 is the estimate of given silviculture "uneven-aged Layer 1-Mature" component tree species percentage within the forest cover polygon.		
640	S1_SPECIES_AGE_2	NULL	NUMBER(5,0)
	The S1 SPECIES AGE 2 is the average age of the given silviculture "uneven-aged Layer 1-Mature" component tree species percent within the forest cover polygon		
650	S1_SPECIES_HEIGHT_2	NULL	NUMBER(3,1)
	The S1 SPECIES HEIGHT 2 is the average height of the given silviculture "uneven-aged Layer 1-Mature" component leading tree species in metres.		
660	S1_SPECIES_CODE_3	NULL	VARCHAR2(8)
	The S1 SPECIES CODE 3 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 1-Mature" component		
670	S1_SPECIES_PERCENT_3	NULL	NUMBER(3,0)
	The S1 SPECIES PERCENT 3 is the estimate of given silviculture "uneven-aged Layer 1-Mature" component tree species percentage within the forest cover polygon.		
680	S1_SPECIES_CODE_4	NULL	VARCHAR2(8)
	The S1 SPECIES CODE 4 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 1-Mature" component		
690	S1_SPECIES_PERCENT_4	NULL	NUMBER(3,0)
	The S1 SPECIES PERCENT 4 is the estimate of given silviculture "uneven-aged Layer 1-Mature" component tree species percentage within the forest cover polygon.		
700	S1_SPECIES_CODE_5	NULL	VARCHAR2(8)
	The S1 SPECIES CODE 5 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 1-Mature" component		
710	S1_SPECIES_PERCENT_5	NULL	NUMBER(3,0)
	The S1 SPECIES PERCENT 5 is the estimate of given silviculture "uneven-aged Layer 1-Mature"		

Table: RSLT_FOREST_COVER_SILV_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	component tree species percentage within the forest cover polygon.		
720	S1_MORE_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	The S1 MORE SPECIES EXIST IND is 'Y' when this layer contains more than 5 species records; these records are available in RSLT FOREST COVER SPECIES.		
730	S1_SILV_LABEL	NULL	VARCHAR2(160)
	The S1 SILV LABEL is the silviculture Label for "uneven-aged Layer 1-Mature" forest cover polygon		
740	S2_FOREST_COVER_LAYER_ID	NULL	NUMBER(10,0)
	The S2 FOREST COVER LAYER ID is a RESULTS system-generated unique identifier for the layer information.		
750	S2_TOTAL_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S2 TOTAL STEMS PER HA is the total stems per hectare for the "uneven-aged Layer 2-Pole" forest cover polygon.		
760	S2_TOTAL_WELL_SPACED_STEMS_HA	NULL	NUMBER(10,0)
	The S2 TOTAL WELL SPACED STEMS HA is the total number of well-spaced stems per hectare for the "uneven-aged Layer 2-Pole" forest cover polygon. Stems density for silviculture layer disregarding the M-value.		
770	S2_WELL_SPACED_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S2 TOTAL WELL SPACED STEMS HA is the number of well-spaced stems per hectare for "uneven-aged Layer 2-Pole" forest cover polygon. Trees are healthy, preferred or acceptable species and well - spaced using the minimum inter-tree distance in the stocking standards (as defined by the SU Identifier).		
780	S2_FREE_GROWING_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S2 FREE GROWING STEMS PER HA is the number of free-growing stems per hectare for "uneven-aged Layer 2-Pole" forest cover polygon. Free growing stem density for the silviculture (based on the M-value). Free growing trees are healthy, preferred, or acceptable species, well-spaced, free from inhibiting brush, and meet or exceed the minimum height (if applicable).		
790	S2_CROWN_CLOSURE_PERCENT	NULL	NUMBER(3,0)
	The S2 CROWN CLOSURE PERCENT represents the closing together of the crowns of trees in a forest as they age and grow effectively blocking sunlight from reaching the forest floor for "uneven-aged Layer 2-Pole" forest cover polygon.		
800	S2_BASAL_AREA	NULL	NUMBER(5,0)
	The S2 BASAL AREA is the cumulative cross-sectional residual basal area of all stems >12.5cm dbh for "uneven-aged Layer 2-Pole" forest cover polygon. Required if basal area is a part of stocking standard.		
810	S2_SPECIES_CODE_1	NULL	VARCHAR2(8)
	The S2 SPECIES CODE 1 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 2-Pole" component		
820	S2_SPECIES_PERCENT_1	NULL	NUMBER(3,0)
	The S2 SPECIES PERCENT 1 is the estimate of given silviculture "uneven-aged Layer 2-Pole" component tree species percentage within the forest cover polygon.		
830	S2_SPECIES_AGE_1	NULL	NUMBER(5,0)
	The S2 SPECIES AGE 1 is the average age of the given silviculture "uneven-aged Layer 2-Pole" component tree species percent within the forest cover polygon		
840	S2_SPECIES_HEIGHT_1	NULL	NUMBER(3,1)
	The S2 SPECIES HEIGHT 1 is the average height of the given silviculture "uneven-aged Layer 2-Pole" component leading tree species in metres.		
850	S2_SPECIES_CODE_2	NULL	VARCHAR2(8)
	The S2 SPECIES CODE 2 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 2-Pole" component		
860	S2_SPECIES_PERCENT_2	NULL	NUMBER(3,0)
	The S2 SPECIES PERCENT 2 is the estimate of given silviculture "uneven-aged Layer 2-Pole" component tree species percentage within the forest cover polygon.		
870	S2_SPECIES_AGE_2	NULL	NUMBER(5,0)
	The S2 SPECIES AGE 2 is the average age of the given silviculture "uneven-aged Layer 2-Pole" component tree species percent within the forest cover polygon		
880	S2_SPECIES_HEIGHT_2	NULL	NUMBER(3,1)
	The S2 SPECIES HEIGHT 2 is the average height of the given silviculture "uneven-aged Layer 2-Pole" component leading tree species in metres.		
890	S2_SPECIES_CODE_3	NULL	VARCHAR2(8)

Table: RSLT_FOREST_COVER_SILV_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	The S2 SPECIES CODE 3 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 2-Pole" component		
900	S2_SPECIES_PERCENT_3	NULL	NUMBER(3,0)
	The S2 SPECIES PERCENT 3 is the estimate of given silviculture "uneven-aged Layer 2-Pole" component tree species percentage within the forest cover polygon.		
910	S2_SPECIES_CODE_4	NULL	VARCHAR2(8)
	The S2 SPECIES CODE 4 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 2-Pole" component		
920	S2_SPECIES_PERCENT_4	NULL	NUMBER(3,0)
	The S2 SPECIES PERCENT 4 is the estimate of given silviculture "uneven-aged Layer 2-Pole" component tree species percentage within the forest cover polygon.		
930	S2_SPECIES_CODE_5	NULL	VARCHAR2(8)
	The S2 SPECIES CODE 5 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 2-Pole" component		
940	S2_SPECIES_PERCENT_5	NULL	NUMBER(3,0)
	The S2 SPECIES PERCENT 5 is the estimate of given silviculture "uneven-aged Layer 2-Pole" component tree species percentage within the forest cover polygon.		
950	S2_MORE_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	The S2 MORE SPECIES EXIST IND is 'Y' when this layer contains more than 5 species records; these records are available in RSLT FOREST COVER SPECIES.		
960	S2_SILV_LABEL	NULL	VARCHAR2(160)
	The S2 SILV LABEL is the silviculture Label for "uneven-aged Layer 2-Pole" forest cover polygon		
970	S3_FOREST_COVER_LAYER_ID	NULL	NUMBER(10,0)
	The S3 FOREST COVER LABEL ID is a RESULTS system-generated unique identifier for the layer information.		
980	S3_TOTAL_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S3 TOTAL STEMS PER HA is the total stems per hectare for the "uneven-aged Layer 3-Sapling" forest cover polygon.		
990	S3_TOTAL_WELL_SPACED_STEMS_HA	NULL	NUMBER(10,0)
	The S3 TOTAL WELL SPACED STEMS HA is the total number of well-spaced stems per hectare for the "uneven-aged Layer 3-Sapling" forest cover polygon. Stems density for silviculture layer disregarding the M-value.		
1000	S3_WELL_SPACED_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S3 WELL SPACED STEMS PER HA is the number of well-spaced stems per hectare for "uneven-aged Layer 3-Sapling" forest cover polygon. Trees are healthy, preferred or acceptable species and well - spaced using the minimum inter-tree distance in the stocking standards (as defined by the SU Identifier).		
1010	S3_FREE_GROWING_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S3 FREE GROWING STEMS PER HA is the number of free-growing stems per hectare for "uneven-aged Layer 3-Sapling" forest cover polygon. Free growing stem density for the silviculture (based on the M-value). Free growing trees are healthy, preferred, or acceptable species, well-spaced, free from inhibiting brush, and meet or exceed the minimum height (if applicable).		
1020	S3_CROWN_CLOSURE_PERCENT	NULL	NUMBER(3,0)
	The S3 CROWN CLOSURE PERCENT represents the closing together of the crowns of trees in a forest as they age and grow effectively blocking sunlight from reaching the forest floor for "uneven-aged Layer 3-Sapling" forest cover polygon.		
1030	S3_BASAL_AREA	NULL	NUMBER(5,0)
	The S3 BASAL AREA is the cumulative cross-sectional residual basal area of all stems >12.5cm dbh for "uneven-aged Layer 3-Sapling" forest cover polygon. Required if basal area is a part of stocking standard.		
1040	S3_SPECIES_CODE_1	NULL	VARCHAR2(8)
	The S3 SPECIES CODE 1 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 3-Sapling" component		
1050	S3_SPECIES_PERCENT_1	NULL	NUMBER(3,0)
	The S3 SPECIES PERCENT 1 is the estimate of given silviculture "uneven-aged Layer 3-Sapling" component tree species percentage within the forest cover polygon.		
1060	S3_SPECIES_AGE_1	NULL	NUMBER(5,0)
	The S3 SPECIES AGE 1 is the average age of the given silviculture "uneven-aged Layer 3-Sapling" component tree species percent within the forest cover polygon		

Table: RSLT_FOREST_COVER_SILV_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
1070	S3_SPECIES_HEIGHT_1	NULL	NUMBER(3,1)
	The S3 SPECIES HEIGHT 1 is the average height of the given silviculture "uneven-aged Layer 3-Sapling" component leading tree species in metres.		
1080	S3_SPECIES_CODE_2	NULL	VARCHAR2(8)
	The S3 SPECIES CODE 2 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 3-Sapling" component		
1090	S3_SPECIES_PERCENT_2	NULL	NUMBER(3,0)
	The S3 SPECIES PERCENT 2 is the estimate of given silviculture "uneven-aged Layer 3-Sapling" component tree species percentage within the forest cover polygon.		
1100	S3_SPECIES_AGE_2	NULL	NUMBER(5,0)
	The S3 SPECIES AGE 2 is the average age of the given silviculture "uneven-aged Layer 3-Sapling" component tree species percent within the forest cover polygon		
1110	S3_SPECIES_HEIGHT_2	NULL	NUMBER(3,1)
	The S3 SPECIES HEIGHT 2 is the average height of the given silviculture "uneven-aged Layer 3-Sapling" component leading tree species in metres.		
1120	S3_SPECIES_CODE_3	NULL	VARCHAR2(8)
	The S3 SPECIES CODE 3 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 3-Sapling" component		
1130	S3_SPECIES_PERCENT_3	NULL	NUMBER(3,0)
	The S3 SPECIES PERCENT 3 is the estimate of given silviculture "uneven-aged Layer 3-Sapling" component tree species percentage within the forest cover polygon.		
1140	S3_SPECIES_CODE_4	NULL	VARCHAR2(8)
	The S3 SPECIES CODE 4 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 3-Sapling" component		
1150	S3_SPECIES_PERCENT_4	NULL	NUMBER(3,0)
	The S3 SPECIES PERCENT 4 is the estimate of given silviculture "uneven-aged Layer 3-Sapling" component tree species percentage within the forest cover polygon.		
1160	S3_SPECIES_CODE_5	NULL	VARCHAR2(8)
	The S3 SPECIES CODE 5 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 3-Sapling" component		
1170	S3_SPECIES_PERCENT_5	NULL	NUMBER(3,0)
	The S3 SPECIES PERCENT 5 is the estimate of given silviculture "uneven-aged Layer 3-Sapling" component tree species percentage within the forest cover polygon.		
1180	S3_MORE_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	The S3 MORE SPECIES EXIST IND is 'Y' when this layer contains more than 5 species records; these records are available in RSLT FOREST COVER SPECIES.		
1190	S3_SILV_LABEL	NULL	VARCHAR2(160)
	The S3 SILV LABEL is the silviculture Label for "uneven-aged Layer 3-Sapling" forest cover polygon		
1200	S4_FOREST_COVER_LAYER_ID	NULL	NUMBER(10,0)
	The S4 FOREST COVER LAYER ID is a RESULTS system-generated unique identifier for the layer information.		
1210	S4_TOTAL_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S4 TOTAL STEMS PER HA is the total stems per hectare for the "uneven-aged Layer 4-Regen" forest cover polygon.		
1220	S4_TOTAL_WELL_SPACED_STEMS_HA	NULL	NUMBER(10,0)
	The S4 TOTAL WELL SPACED STEMS HA is the total number of well-spaced stems per hectare for the "uneven-aged Layer 4-Regen" forest cover polygon. Stems density for silviculture layer disregarding the M-value.		
1230	S4_WELL_SPACED_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S4 WELL SPACED STEMS PER HA is the number of well-spaced stems per hectare for "uneven-aged Layer 4-Regen" forest cover polygon. Trees are healthy, preferred or acceptable species and well - spaced using the minimum inter-tree distance in the stocking standards (as defined by the SU Identifier).		
1240	S4_FREE_GROWING_STEMS_PER_HA	NULL	NUMBER(10,0)
	The S4 FREE GROWING STEMS PER HA is the number of free-growing stems per hectare for "uneven-aged Layer 4-Regen" forest cover polygon. Free growing stem density for the silviculture (based on the M-value). Free growing trees are healthy, preferred, or acceptable species, well-spaced, free from inhibiting brush, and meet or exceed the minimum height (if applicable).		

Table: RSLT_FOREST_COVER_SILV_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
1250	S4_CROWN_CLOSURE_PERCENT	NULL	NUMBER(3,0)
	The S4 CROWN CLOSURE PERCENT represents the closing together of the crowns of trees in a forest as they age and grow effectively blocking sunlight from reaching the forest floor for "uneven-aged Layer 4-Regen" forest cover polygon.		
1260	S4_BASAL_AREA	NULL	NUMBER(5,0)
	The S4 BASAL AREA is the cumulative cross-sectional residual basal area of all stems >12.5cm dbh for "uneven-aged Layer 4-Regen" forest cover polygon. Required if basal area is a part of stocking standard.		
1270	S4_SPECIES_CODE_1	NULL	VARCHAR2(8)
	The S4 SPECIES PERCENT 1 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 4-Regen" component		
1280	S4_SPECIES_PERCENT_1	NULL	NUMBER(3,0)
	The S4 SPECIES PERCENT 1 is the estimate of given silviculture "uneven-aged Layer 4-Regen" component tree species percentage within the forest cover polygon.		
1290	S4_SPECIES_AGE_1	NULL	NUMBER(5,0)
	The S4 SPECIES AGE 1 is the average age of the given silviculture "uneven-aged Layer 4-Regen" component tree species percent within the forest cover polygon		
1300	S4_SPECIES_HEIGHT_1	NULL	NUMBER(3,1)
	The S4 SPECIES HEIGHT 1 is the average height of the given silviculture "uneven-aged Layer 4-Regen" component leading tree species in metres.		
1310	S4_SPECIES_CODE_2	NULL	VARCHAR2(8)
	The S4 SPECIES CODE represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 4-Regen" component		
1320	S4_SPECIES_PERCENT_2	NULL	NUMBER(3,0)
	The S4 SPECIES PERCENT 2 is the estimate of given silviculture "uneven-aged Layer 4-Regen" component tree species percentage within the forest cover polygon.		
1330	S4_SPECIES_AGE_2	NULL	NUMBER(5,0)
	The S4 SPECIES AGE 2 is the average age of the given silviculture "uneven-aged Layer 4-Regen" component tree species percent within the forest cover polygon		
1340	S4_SPECIES_HEIGHT_2	NULL	NUMBER(3,1)
	The S4 SPECIES HEIGHT 2 is the average height of the given silviculture "uneven-aged Layer 4-Regen" component leading tree species in metres.		
1350	S4_SPECIES_CODE_3	NULL	VARCHAR2(8)
	The S4 SPECIES CODE 3 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 4-Regen" component		
1360	S4_SPECIES_PERCENT_3	NULL	NUMBER(3,0)
	The S4 SPECIES PERCENT 3 is the estimate of given silviculture "uneven-aged Layer 4-Regen" component tree species percentage within the forest cover polygon.		
1370	S4_SPECIES_CODE_4	NULL	VARCHAR2(8)
	The S4 SPECIES PERCENT 4 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 4-Regen" component		
1380	S4_SPECIES_PERCENT_4	NULL	NUMBER(3,0)
	The S4 SPECIES PERCENT 4 is the estimate of given silviculture "uneven-aged Layer 4-Regen" component tree species percentage within the forest cover polygon.		
1390	S4_SPECIES_CODE_5	NULL	VARCHAR2(8)
	The S4 SPECIES CODE 5 represents the tree species (primary, secondary, tertiary, etc.) with the forest cover polygon for the silviculture "uneven-aged Layer 4-Regen" component		
1400	S4_SPECIES_PERCENT_5	NULL	NUMBER(3,0)
	The S4 SPECIES PERCENT 5 is the estimate of given silviculture "uneven-aged Layer 4-Regen" component tree species percentage within the forest cover polygon.		
1410	S4_MORE_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	The S4 MORE SPECIES EXIST IND is 'Y' when this layer contains more than 5 species records; these records are available in RSLT FOREST COVER SPECIES.		
1420	S4_SILV_LABEL	NULL	VARCHAR2(160)
	The S4 SILV LABEL is the Silviculture Label for "uneven-aged Layer 4-Regen" forest cover polygon		
1430	GEOMETRY_EXIST_IND	NULL	VARCHAR2(1)
	The GEOMETRY EXIST IND indicates if there is geometry for the opening. A value of 'Y' indicates there is geometry. A value of 'N' indicates there is no geometry.		

Table: RSLT_FOREST_COVER_SILV_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
1435	FEATURE_AREA	NULL	NUMBER(11,4)
	The FEATURE AREA is the area of the feature in square meters.		
1440	FEATURE_PERIMETER	NULL	NUMBER(11,4)
	The FEATURE PERIMETER is the perimeter of the feature in meters.		
1450	CAPTURE_METHOD_CODE	NULL	VARCHAR2(30)
	The CAPTURE METHOD CODE is a code defining the capture method. (e.g. digitize).		
1460	DATA_SOURCE_CODE	NULL	VARCHAR2(10)
	The DATA SOURCE CODE is a code defining the source of the spatial feature (e.g. GPS, TRIM).		
1470	OBSERVATION_DATE	NULL	DATE
	The OBSERVATION DATE is the geometry collection date.		
1480	DATA_QUALITY_COMMENT	NULL	VARCHAR(255)
	The DATA QUALITY COMMENT is a comment indicating the Geometry accuracy.		
1490	FOREST_COVER_WHO_CREATED	NOT NULL	VARCHAR2(30)
	The FOREST COVER WHO CREATED is the USERID of the individual who created the activity record.		
1500	FOREST_COVER_WHEN_CREATED	NOT NULL	DATE
	The FOREST COVER WHO UPDATED is the date and time when the activity record was created.		
1510	FOREST_COVER_WHO_UPDATED	NOT NULL	VARCHAR2(30)
	The FOREST COVER WHEN UPDATED is the USERID of the individual who last updated the activity record.		
1520	FOREST_COVER_WHEN_UPDATED	NOT NULL	DATE
	THE FOREST COVER WHEN UPDATED is the date and time when the activity record was last updated.		
1530	FEATURE_CLASS_SKEY	NULL	NUMBER(10,0)
	The FEATURE CLASS SKEY is the unique key assigned to a Feature Class by the Ministry of Forests.		
1540	GEOMETRY	NULL	
	The GEOMETRY is the Forest Cover geographical representation.		
1550	OBJECTID	NOT NULL	NUMBER(10,0)
	The OBJECTID is a system generated value uniquely identifying the opening. Used by SDE.		

Table: RSLT_FOREST_COVER_SPECIES

Description:

The tree species contained within RESULT's FOREST COVER inventory and silviculture components.

Columns:

	Seq.	Column	Nulls?	Type
*	10	FOREST_COVER_ID	NOT NULL	NUMBER(10,0)
		The FOREST COVER ID is a system-generated value by RESULTS to uniquely identify forest cover polygon.		
*	20	FOREST_COVER_LAYER_ID	NOT NULL	NUMBER(10,0)
		The FOREST COVER LAYER ID is a RESULTS system-generated unique identifer for the layer information.		
*	30	SPECIES_ORDER	NOT NULL	NUMBER(2,0)
		The SPECIES ORDER is a system-generated increment in ascending order to track the number of tree species submitted per forest cover layer. The species order number in descending percent order.		
*	40	TREE_SPECIES_CODE	NOT NULL	VARCHAR2(8)
		The TREE SPECIES CODE represents the tree species within the polygon. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
	50	TREE_SPECIES_PERCENT	NULL	NUMBER(3,0)
		The TREE SPECIES PERCENT is the estimate given to the tree species percentage within the polygon.		
	60	AVERAGE_AGE	NULL	NUMBER(5,0)
		The AVERAGE AGE is the given component/layer leading tree species in years.		
	70	AVERAGE_HEIGHT	NULL	NUMBER(3,1)
		The AVERAGE HEIGHT is the given component/layer leading species in metres.		
	1020	FCS_WHO_CREATED	NOT NULL	VARCHAR2(30)
		The FCS WHO CREATED is the USERID of the individual who created the forest cover record.		
	1060	FCS_WHEN_CREATED	NOT NULL	DATE
		The FCS WHEN CREATED is the date and time when the forest cover record was created.		
	1070	FCS_WHO_UPDATED	NOT NULL	VARCHAR2(30)
		The FCS WHO UPDATED is the USERID of the individual who last updated the forest cover record.		
	1080	FCS_WHEN_UPDATED	NOT NULL	DATE
		The FCS WHEN UPDATED is the date and time when the forest cover record was last updated.		
	1090	CHANGE_TIMESTAMP1	NOT NULL	DATE
		The date and time of the last update to the FOREST COVER table.		

Table: RSLT_FOREST_COVER_SPECIES_VW

Description:

The tree species contained within RESULT's FOREST COVER inventory and silviculture components.

Columns:

Seq.	Column	Nulls?	Type
10	FOREST_COVER_ID	NOT NULL	NUMBER(10,0)
	The FOREST COVER ID is a system-generated value by RESULTS to uniquely identify forest cover polygon.		
20	FOREST_COVER_LAYER_ID	NOT NULL	NUMBER(10,0)
	The FOREST COVER LAYER ID is a RESULTS system-generated unique identifer for the layer information.		
30	SPECIES_ORDER	NOT NULL	NUMBER(2,0)
	The SPECIES ORDER is a system-generated increment in ascending order to track the number of tree species submitted per forest cover layer. The species order number in descending percent order.		
40	TREE_SPECIES_CODE	NOT NULL	VARCHAR2(8)
	The TREE SPECIES CODE represents the tree species within the polygon.		
50	TREE_SPECIES_PERCENT	NULL	NUMBER(3,0)
	The TREE SPECIES PERCENT is the estimate given to the tree species percentage within the polygon.		
60	AVERAGE_AGE	NULL	NUMBER(5,0)
	The AVERAGE AGE is the given component/layer leading tree species in years.		
70	AVERAGE_HEIGHT	NULL	NUMBER(3,1)
	The AVERAGE HEIGHT is the given component/layer leading species in metres.		
80	FCS_WHO_CREATED	NOT NULL	VARCHAR2(30)
	The FCS WHO CREATED is the USERID of the individual who created the forest cover record.		
90	FCS_WHEN_CREATED	NOT NULL	DATE
	The FCS WHEN CREATED is the date and time when the forest cover record was created.		
100	FCS_WHO_UPDATED	NOT NULL	VARCHAR2(30)
	The FCS WHO UPDATED is the USERID of the individual who last updated the forest cover record.		
110	FCS_WHEN_UPDATED	NOT NULL	DATE
	The FCS WHEN UPDATED is the date and time when the forest cover record was last updated.		

Table: RSLT_OPENING_POLYGON

Description:

The spatial representation for an opening, which is an administration boundary representing an area that had been harvested or disturbed where there are forest management activities.

Columns:

Seq.	Column	Nulls?	Type
* 10	OPENING_ID	NOT NULL	NUMBER(10,0)
	The OPENING ID is a system generated value by RESULTS to uniquely identify the opening.		
20	MAPSHEET_GRID	NULL	VARCHAR2(3)
	The MAPSHEET GRID refers to NTG or BCGS grid. Values are 82, 83, 92, 93, 94, 95, 102, 103,104, 114.		
30	MAPSHEET_LETTER	NULL	VARCHAR2(1)
	The MAPSHEET LETTER is the NTG/BCGS letter. Values are A-P, and W.		
40	MAPSHEET_SQUARE	NULL	VARCHAR2(3)
	The MAPSHEET SQUARE represents the BCGS number or NTG number and letter. For BCGS numbers are 1-100, and for NTG numbers and letters values are 1-16 and A-H and W respectively.		
50	MAPSHEET	NULL	VARCHAR2(7)
	The MAPSHEET is the full BCGS Mapsheet identifier. Eg. 92G100		
60	OPENING_NUMBER	NULL	VARCHAR2(4)
	The OPENING NUMBER is a unique four character field that is assigned to an opening on a specified mapsheet. Ex. ' 514'		
65	MAP_LABEL	NULL	VARCHAR2(12)
	The default label to be used when displaying the feature on a map. Consists of the MAPSHEET GRID, MAPSHEET LETTER, MAPSHEET SQUARE, and OPENING NUMBER.		
70	OPENING_CATEGORY_CODE	NOT NULL	VARCHAR2(7)
	The OPENING CATEGORY CODE indicates who holds the obligation and the extent and nature of the obligation. Eg. FTML - Forest Tenure Major Licensee; NDFS - Natural Disturbance Forest Service.		
80	OPENING_STATUS_CODE	NOT NULL	VARCHAR2(3)
	The OPENING STATUS CODE indicates whether the opening is or is not free growing based on all standards units being declared free growing. It also is used to tracked specific pending administrative and legal processes. Eg. APP-Approved, FG-Free Growing; SUB-Submitted; AMD-Amending Silviculture Prescription.		
90	OPENING_LOCATION_NAME	NULL	VARCHAR2(30)
	The OPENING LOCATION NAME identifies the location name for the opening that is assigned by user. Eg. Peterson Creek.		
100	DISTRICT_ADMIN_ZONE	NULL	VARCHAR2(2)
	The DISTRICT ADMIN ZONE represents different administrative zones within the district. These District Admin Zones are created and managed by MOF district staff to assist with district work events.		
110	LICENSEE_OPENING_ID	NULL	VARCHAR2(30)
	The LICENSEE OPENING ID is a unique identifier provided by the Licensee to identify the Opening Number.		
120	MAX_ALLOW_PERMNT_ACCESS_PCT	NULL	NUMBER(3,1)
	The MAX ALLOW PERMNT ACCESS PCT is the maximum allowable permanent access percent is the total maximum percentage of the gross area of the opening that can be occupied by permanent access structures. Includes roads, landing, gravel pits, burrow pits, and permanent trails.		
130	APPROVE_DATE	NULL	DATE
	The APPROVAL DATE refers to the silviculture prescription approval date. For site plans, the approval date is auto-generated based on the first opening submission.		
140	TSB_NUMBER_CODE	NULL	VARCHAR2(3)
	The TSB NUMBER CODE is the Timber Supply Block that is manually assigned to the opening. For any tenured openings reference can be made using the Management Unit Code and ID. Example: 17A; 18B.		
150	AMENDMENT_IND	NULL	VARCHAR2(1)
	The AMENDMENT IND indicates if there had been amendments made to the silviculture prescription or site plan on the opening. A value of 'Y' means there have been amendments. A value of 'N' means there have been no amendments.		
160	PREV_TREE_SPECIES1_CODE	NULL	VARCHAR2(8)
	The PREV TREE SPECIES1 CODE identifies the dominant species of the stand before harvest from the previous forest cover inventory label of the largest polygon in the opening. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
170	PREV_TREE_SPECIES2_CODE	NULL	VARCHAR2(8)

Table: RSLT_OPENING_POLYGON (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	The PREV TREE SPECIES2 CODE identifies the second species of the stand before harvest from the previous forest cover inventory label of the largest polygon in the opening. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		
180	PREV_STOCKING_STATUS_CODE	NULL	VARCHAR2(3)
	The PREV STOCKING STATUS CODE is obtained from the previous stand forest cover inventory label of the largest polygon in the opening. Example: IMM-Immature, MAT-Mature, etc.		
190	PREV_AGE_CLASS_CODE	NULL	VARCHAR2(1)
	The PREV AGE CLASS CODE is obtained from the previous stand forest cover inventory label of the largest polygon in the opening. Age classes are intervals, or ranges, or ages into which trees, forest, stands or forest types are classified. Ex. 1-'1 - 20 Years'; 9-'251 + Years'; etc.		
200	PREV_HEIGHT_CLASS_CODE	NULL	VARCHAR2(1)
	The PREV HEIGHT CLASS CODE is obtained from the previous stand forest cover inventory label of the largest polygon in the opening. Height classes represents intervals into range of trees or stand heights are classified. Example: 1-'0 - 10.4 Meters'; 8-'64.5 + Meters'; etc.		
210	PREV_SITE_INDEX	NULL	NUMBER(5,0)
	The PREV SITE INDEX is obtained from the leading species of the previous stand forest cover inventory label of the largest polygon in the opening. Estimates forest land productivity.		
220	PREV_SITE_INDEX_SOURCE_CODE	NULL	VARCHAR2(1)
	The PREV SITE INDEX SOURCE CODE describes the source or origin of the previous site index obtained from the leading species of the previous stand forest cover inventory label of the largest polygon in the opening. Example: C-site index from site index curve.		
240	RESULTS_SUBMISSION_ID	NULL	NUMBER(10,0)
	The RESULTS SUBMISSION ID is a system generated value generated by ESF to link between RESULTS opening data and the ESF submission.		
250	REGION_CODE	NOT NULL	VARCHAR2(6)
	The REGION CODE is the MOFR Region Code that the opening is located in. Example: RCO - Coast Forest Region.		
260	REGION_NAME	NOT NULL	VARCHAR2(100)
	The REGION NAME is the MOFR Region Name that the opening is located in.		
270	DISTRICT_CODE	NOT NULL	VARCHAR2(6)
	The DISTRICT CODE is the MOFR District Code that the opening is located in. Example: DRM-Rocky Mountain Forest District.		
280	DISTRICT_NAME	NOT NULL	VARCHAR2(100)
	The DISTRICT NAME is the MOFR District Name that the opening is located in.		
290	BCTS_CODE	NULL	VARCHAR2(6)
	The BCTS CODE is the BC Timber Sales Organizational Code that the BCTS opening is located in. Example: TKO-Kootenay Timber Sales Office.		
300	BCTS_NAME	NULL	VARCHAR2(100)
	The BCTS NAME is the BC Timber Sales Organizational Name that the BCTS opening is located in.		
310	OPENING_GROSS_AREA	NULL	NUMBER(11,4)
	The OPENING GROSS AREA is the total area (in hectares) that the opening encompasses (e.g., 120 Hectares).		
320	FOREST_FILE_ID	NULL	VARCHAR2(10)
	The FOREST FILE ID represents the licence number of the opening corresponding to the cutting authority. Note where there is more than one tenure associated with the opening, the prime licence is shown. Eg. TFL49, A19204, W0014.		
330	CUTTING_PERMIT_ID	NULL	VARCHAR2(3)
	The CUTTING PERMIT ID is the cutting permit document number that corresponds to the licence associated with the opening. Note where there is more than one tenure associated with the opening, the prime licence is shown. Eg. TFL49, A19204, W0014.		
340	TIMBER_MARK	NULL	VARCHAR2(10)
	The TIMBER MARK is for the opening as shown on the legal document (eg. FT8675, 67801)		
350	CUT_BLOCK_ID	NULL	VARCHAR2(10)
	The CUT BLOCK ID is the approved cutblock identifier for the opening as the legal Exhibit 'A' document. Note where there is more than one tenure associated with the opening, the prime licence is shown. Eg. 1002LM		
360	MGMT_UNIT_ID	NULL	VARCHAR2(4)

Table: RSLT_OPENING_POLYGON (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	The MGMT UNIT ID the opening resides within. This is used in conjunction with Management Unit Type Code. This is auto-generated through tenure linkage based on the prime licence associated with the opening. Eg. U37-Strathcona TSA; T01-TFL01 Port Edward.		
370	MGMT_UNIT_TYPE_CODE	NULL	VARCHAR2(1)
	The MGMT UNIT TYPE CODE identifies the general type of administrative unit. This is often used with Management Unit Id to make reference to MOF administrative management unit. This is auto-generated through tenure linkage based on the prime licence associated with the opening. Eg. U-Timber Supply Area; V-Timber Supply Block; T-Tree Farm Licence; F-Woodlot, etc.		
380	MGMT_UNIT_DESCRIPTION	NULL	VARCHAR2(100)
	The MGMT UNIT DESCRIPTION is the text reference to the specific administrative management unit based on opening's tenure linkage based on the prime licence. (eg. Kamloops TSA).		
390	FILE_TYPE_CODE	NULL	VARCHAR2(3)
	The FILE TYPE CODE is the tenure type associated with the licence. This is based on the opening's tenure prime licence. Eg. A01-Forest Licence; A02-Tree Farm Licence, etc.		
400	DISTURBANCE_START_DATE	NULL	DATE
	The DISTURBANCE START DATE is derived from the first reported disturbance activity reporting. This date is used to calculate the silviculture obligation milestones.		
410	DISTURBANCE_END_DATE	NULL	DATE
	The DISTURBANCE END DATE is derived from the last disturbance activity reporting record based on the disturbance activity's completion date.		
420	CLIENT_NAME	NULL	VARCHAR2(60)
	The CLIENT NAME in RESULTS refers to the opening's prime tenure and identifies the MOFR Client, Company or individual associated who owns the silviculture obligation.		
430	CLIENT_NUMBER	NULL	VARCHAR2(8)
	The Client Number is the Ministry's unique client number assigned to the Client Name. RESULTS refers the client information through the opening's prime tenure.		
440	CLIENT_LOCATION_CODE	NULL	VARCHAR2(2)
	The CLIENT LOCATION CODE is a further specific categorization code for those clients who may have more than one division.		
450	GENERALIZED_BGC_ZONE_CODE	NULL	VARCHAR2(4)
	The GENERALIZED BGC ZONE CODE is the Biogeoclimatic Ecosystem Classification (BEC) system. Eg. IDF; MS; CWH. This is derived from the largest standards unit for the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View. Eg. IDF; MS; CWH. *2002/12/27 HS: Changed the BGC attributes from mandatory to optional.* *Jan 24 2003 wc Changed name from BGC ZONE to BGC ZONE CODE*		
460	GENERALIZED_BGC_SUBZONE_CODE	NULL	VARCHAR2(3)
	The GENERALIZED BGC SUBZONE CODE is the Biogeoclimatic Ecosystem Classification (BEC) system. Eg. dk; xc; mk. This is derived from the largest standards unit for the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View. Eg. dk; xc; mk. *2002/12/27 HS: Changed the BGC attributes from mandatory to optional.* *Jan 24 2003 wc Changed name from BGC SUBZONE to BGC SUBZONE CODE*		
470	GENERALIZED_BGC_VARIANT	NULL	VARCHAR2(1)
	The GENERALIZED BGC VARIANT according to the BEC system. Eg. 1, 2. This is derived from the largest standards unit for the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View. *2002/12/27 HS: Changed the BGC attributes from mandatory to optional.*		
480	GENERALIZED_BGC_PHASE	NULL	VARCHAR2(1)
	The GENERALIZED BGC PHASE according to the BEC system. This is derived from the largest standards units for the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View. *2002/12/27 HS: Changed the BGC attributes from mandatory to optional.*		
490	GENERALIZED_BEC_SITE_SERIES	NULL	VARCHAR2(4)
	The GENERALIZED BEC SITE SERIES for the given biogeoclimatic unit, according to the BEC system. Eg. 01, 04, 05. This is derived from the largest standards unit for the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View. *2002/12/27 HS: Changed the BGC attributes from mandatory to optional.* *Jan 24 2003 wc Change name from BGC SITE SERIES to BEC SITE SERIES*		

Table: RSLT_OPENING_POLYGON (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	2006-02-02 R.A.Robb (Release 3.0) *- modified maxlength from 2 to 4*		
500	GENERALIZED_BEC_SITE_TYPE GENERALIZED BEC SITE TYPE for certain site series, according to the BEC system. This is derived from the largest standards unit from the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View. Eg. MS, NP. *2002/12/27 HS: Changed the BGC attributes from mandatory to optional.* *Jan 24 2003 wc Change name from BGC SITE TYPE to BEC SITE TYPE* *2006-03-21 R.A.Robb (Rls 3.0)* *- changed maxlength from 2 to 3 to match source column* *BEC_SITE_SERIES.SITE_SERIES_PHASE_CD*	NULL	VARCHAR2(3)
510	GENERALIZED_BEC_SERAL GENERALIZED BEC SERIAL for certain site series, according to the BEC system. This is derived from the largest standards unit from the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View. Eg. Accp, Acho. *2006-02-17 R.A.Robb (Rls 2.4)* *- added*	NULL	VARCHAR2(4)
520	DENUDATION_1_DISTURBANCE_CODE The DENUDATION 1 DISTURBANCE CODE is based on the first disturbance activity reported, the disturbance code representing the disturbance origin. Eg. L-Logged, B-Burned, S-Salvage, etc.	NULL	VARCHAR2(3)
530	DENUDATION_1_SILV_SYSTEM_CODE The DENUDATION 1 SILV SYSTEM CODE is based on the first disturbance activity reported, the silvicultural system used for the harvesting activity. Eg. CLEAR-Clearcut; CCRES-Clearcut with reserves; SELEC-Selection, etc.	NULL	VARCHAR2(5)
540	DENUDATION_1_SILV_VARIANT_CODE The DENUDATION 1 SILV VARIANT CODE is based on the first disturbance activity reported, the silvicultural system's variant which describes the distribution or removal pattern of the harvest. Eg. GRP-Group; IRR-Irregular; SIN-Single, etc.	NULL	VARCHAR2(3)
550	DENUDATION_1_CUT_PHASE_CODE The DENUDATION 1 CUT PHASE CODE is based on the first disturbance activity reported, the silvicultural system's cut phase which describes the function of the harvest to extract merchantable timber and regeneration. Eg. GRP-Group; IRR-Irregular; SIN-Single, etc.	NULL	VARCHAR2(5)
560	DENUDATION_1_COMPLETION_DATE The DENUDATION 1 COMPLETION DATE is based on the first disturbance activity reported on the disturbance end date.	NULL	DATE
580	DENUDATION_2_DISTURBANCE_CODE The DENUDATION 2 DISTURBANCE CODE is based on the second disturbance activity reported, the disturbance code representing the disturbance origin. Eg. L-Logged, B-Burned, S-Salvage, etc.	NULL	VARCHAR2(3)
590	DENUDATION_2_SILV_SYSTEM_CODE The DENUDATION 2 SILV SYSTEM CODE is based on the second disturbance activity reported, the silvicultural system used for the harvesting activity. Eg. CLEAR-Clearcut; CCRES-Clearcut with reserves; SELEC-Selection, etc.	NULL	VARCHAR2(5)
600	DENUDATION_2_SILV_VARIANT_CODE The DENUDATION 2 SILV VARIANT CODE is based on the second disturbance activity reported, the silvicultural system's variant which describes the distribution or removal pattern of the harvest. Eg. GRP-Group; IRR-Irregular; SIN-Single, etc.	NULL	VARCHAR2(3)
610	DENUDATION_2_CUT_PHASE_CODE The DENUDATION 2 CUT PHASE CODE is based on the second disturbance activity reported, the silvicultural system's cut phase which describes the function of the harvest to extract merchantable timber and regeneration. Eg. GRP-Group; IRR-Irregular; SIN-Single, etc.	NULL	VARCHAR2(5)
620	DENUDATION_2_COMPLETION_DATE The DENUDATION 2 COMPLETION DATE is based on the second disturbance activity reported on the disturbance end date.	NULL	DATE
630	DENUDATION_COUNT The DENUDATION COUNT is the total number of reported disturbance activities for the opening.	NULL	NUMBER(2,0)
640	SITE_PREP_1_TECHNIQUE_CODE	NULL	VARCHAR2(2)

Table: RSLT_OPENING_POLYGON (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	The SITE PREP 1 TECHNIQUE CODE is based on the first site preparation activity reported. The technique code describes the broad category used with site preparation activity (eg. BU Burn)		
650	SITE_PREP_1_TREATMENT_AREA	NULL	NUMBER(11,1)
	The SITE PREP 1 TREATMENT AREA is the total hectares reported for the first completed site preparation activity. *TPM 2008-08-06 Updated the column type to be NUMBER(11,1) to match its source field.*		
660	SITE_PREP_1_COMPLETION_DATE	NULL	DATE
	The SITE PREP 1 COMPLETION DATE is the completion date of the first completed site preparation activity.		
680	SITE_PREP_2_TECHNIQUE_CODE	NULL	VARCHAR2(2)
	The SITE PREP 2 TECHNIQUE CODE is based on the second site preparation activity reported. The technique code describes the broad category used with site preparation activity (eg. BU Burn)		
690	SITE_PREP_2_TREATMENT_AREA	NULL	NUMBER(11,1)
	The SITE PREP 2 TREATMENT AREA is the total hectares reported for the second completed site preparation activity. *TPM 2008-08-06 Updated the column type to be NUMBER(11,1) to match its source field.*		
700	SITE_PREP_2_COMPLETION_DATE	NULL	DATE
	The SITE PREP 2 COMPLETION DATE is the completion date of the second completed site preparation activity.		
710	SITE_PREP_COUNT	NULL	NUMBER(2,0)
	The SITE PREP COUNT is the total number of completed site preparation activities reported for the opening.		
720	PLANTING_1_TECHNIQUE_CODE	NULL	VARCHAR2(2)
	The PLANTING 1 TECHNIQUE CODE is based on the first planting activity reported. The technique code describes the broad category used with planting activity (eg. PL-Planting; RP-Replanting)		
730	PLANTING_1_TREATMENT_AREA	NULL	NUMBER(11,1)
	The PLANTING 1 TREATMENT AREA is the total hectares reported for the first completed planting activity. *TPM 2008-08-06 Updated the column type to be NUMBER(11,1) to match its source field.*		
740	PLANTING_1_COMPLETION_DATE	NULL	DATE
	The PLANTING 1 COMPLETION DATE is the completion date of the first completed planting activity.		
770	PLANTING_2_TECHNIQUE_CODE	NULL	VARCHAR2(2)
	The PLANTING 2 TECHNIQUE CODE is based on the second planting activity reported. The technique code describes the broad category used with planting activity (eg. PL-Planting; RP-Replanting)		
780	PLANTING_2_TREATMENT_AREA	NULL	NUMBER(11,1)
	The PLANTING 2 TREATMENT AREA is the total hectares reported for the second completed planting activity. *TPM 2008-08-06 Updated the column type to be NUMBER(11,1) to match its source field.*		
790	PLANTING_2_COMPLETION_DATE	NULL	DATE
	The PLANTING 2 COMPLETION DATE is the completion date of the second completed planting activity.		
810	PLANTING_COUNT	NULL	NUMBER(2,0)
	The PLANTING COUNT is the total number of completed planting activity reported for the opening.		
820	BRUSHING_TECHNIQUE_CODE	NULL	VARCHAR2(2)
	The BRUSHING TECHNIQUE CODE is based on the first brushing activity reported. The technique code describes the broad category used with brushing activity (eg. MA-Manual; ME-Mechanical)		
830	BRUSHING_TREATMENT_AREA	NULL	NUMBER(11,1)
	The BRUSHING TREATMENT AREA is the total hectares reported for the first completed brushing activity. *TPM 2008-08-06 Updated the column type to be NUMBER(11,1) to match its source field.*		
840	BRUSHING_COMPLETION_DATE	NULL	DATE
	The BRUSHING COMPLETION DATE is the completion date of the first completed brushing activity.		
850	BRUSHING_COUNT	NULL	NUMBER(2,0)
	The BRUSHING COUNT is the total number of completed brushing activity reported for the opening.		
860	SPACING_TREATMENT_AREA	NULL	NUMBER(11,1)
	The SPACING TREATMENT AREA is the total hectares reported for the first completed spacing activity. *TPM 2008-08-06 Updated the column type to be NUMBER(11,1) to match its source field.*		
870	SPACING_COMPLETION_DATE	NULL	DATE
	The SPACING COMPLETION DATE is the completion date of the first completed spacing activity.		

Table: RSLT_OPENING_POLYGON (cont'd)

Columns:

Seq.	Column	Nulls?	Type
880	SPACING_COUNT	NULL	NUMBER(2,0)
	The SPACING COUNT is the total number of completed spacing activity reported for the opening.		
890	FERTILIZATION_TREATMENT_AREA	NULL	NUMBER(11,1)
	The FERTILIZATION TREATMENT AREA is the total hectares reported for the first completed fertilization activity.		
	TPM 2008-08-06 Updated the column type to be NUMBER(11,1) to match its source field.		
900	FERTILIZATION_COMPLETION_DATE	NULL	DATE
	The FERTILIZATION COMPLETION DATE is the completion date of the first completed fertilization activity.		
910	FERTILIZATION_COUNT	NULL	NUMBER(2,0)
	The FERTILIZATION COUNT is the total number of completed fertilization activity reported for the opening.		
920	PRUNING_TREATMENT_AREA	NULL	NUMBER(11,1)
	The PRUNING TREATMENT AREA is the total hectares reported for the first completed pruning activity.		
	TPM 2008-08-06 Updated the column type to be NUMBER(11,1) to match its source field.		
930	PRUNING_COMPLETION_DATE	NULL	DATE
	The PRUNING COMPLETION DATE is the completion date of the first completed pruning activity.		
940	PRUNING_COUNT	NULL	NUMBER(2,0)
	The PRUNING COUNT is the total number of completed pruning activities reported for the opening.		
950	GEOMETRY_EXIST_IND	NULL	VARCHAR2(1)
	The GEOMETRY EXIST IND indicates if there is geometry for the opening. A value of 'Y' indicates there is geometry. A value of 'N' indicates there is no geometry.		
960	FEATURE_AREA	NULL	NUMBER(11,4)
	The FEATURE AREA is the area of the opening in hectares.		
970	FEATURE_PERIMETER	NULL	NUMBER(11,4)
	The FEATURE PERIMETER is the perimeter of the opening in kilometers.		
980	CAPTURE_METHOD_CODE	NULL	VARCHAR2(30)
	The CAPTURE METHOD CODE is a code defining the capture method. (e.g. digitize).		
990	DATA_SOURCE_CODE	NULL	VARCHAR2(10)
	The DATA SOURCE CODE is a code defining the source of the spatial feature (e.g. GPS, TRIM).		
1000	OBSERVATION_DATE	NULL	DATE
	The OBSERVATION DATE is the geometry collection date.		
1010	DATA_QUALITY_COMMENT	NULL	VARCHAR(255)
	The DATA QUALITY COMMENT is a comment indicating the Geometry accuracy.		
1020	SUBMITTED_BY_USERID	NULL	VARCHAR2(30)
	The SUBMITTED BY USER ID is the USERID of the person who submitted the ESF information for the opening.		
	2006-01-12 R.A.Robb (Rls 3.0)		
	- added column		
1030	SUBMITTED_DATE	NULL	DATE
	The SUBMITTED DATE is the date and time when ESF submitted for the opening.		
	2006-01-12 R.A.Robb (Rls 3.0)		
	- added column		
1040	OPENING_WHO_CREATED	NOT NULL	VARCHAR2(30)
	The OPENING WHO CREATED is the USERID of the individual who created the opening record.		
1050	OPENING_WHEN_CREATED	NOT NULL	DATE
	The OPENING WHEN CREATED is the date and time when the opening record was created.		
1060	OPENING_WHO_UPDATED	NOT NULL	VARCHAR2(30)
	The OPENING WHO UPDATED is the USERID of the individual who last updated the opening record.		
1070	OPENING_WHEN_UPDATED	NOT NULL	DATE
	The OPENING WHEN UPDATED is the date and time when the opening record was last updated.		
1080	CHANGE_TIMESTAMP1	NOT NULL	DATE
	The date and time of the last update to the OPENING table.		
1090	CHANGE_TIMESTAMP2	NULL	DATE
	The date and time of the last update to the OPENING GEOMETRY table.		
1100	CHANGE_TIMESTAMP3	NULL	DATE
	The date and time of the last update to the STOCKING ECOLOGY table.		

Table: RSLT_OPENING_POLYGON (cont'd)

Columns:

Seq.	Column	Nulls?	Type
1110	CHANGE_TIMESTAMP4	NULL	DATE
	The date and time of the last update to the ACTIVTY TREATMENT UNIT table.		
1120	FEATURE_CLASS_SKEY	NULL	NUMBER(10,0)
	The FEATURE CLASS SKEY is the unique key assigned to a Feature Class by the Ministry of Forests.		
1125	GEOMETRY	NULL	
	The GEOMETRY is the opening geographical representation.		
1130	OBJECTID	NOT NULL	INTEGER
	The OBJECTID is a system generated value uniquely identifying the opening. Used by SDE.		

Unique Constraints:

RSLT_OPEN_UK
- OBJECTID

Indexes:

RSLT_OPEN_CB_I
- FOREST_FILE_ID
- CUTTING_PERMIT_ID
- CUT_BLOCK_ID

RSLT_OPEN_GEOM_I
- GEOMETRY

Table: RSLT_OPENING_SVW

Description:

The spatial representation for an opening, which is an administration boundary representing an area that had been harvested or disturbed where there are forest management activities.

Columns:

Seq.	Column	Nulls?	Type
10	OPENING_ID	NOT NULL	NUMBER(10,0)
	The OPENING ID is a system generated value by RESULTS to uniquely identify the opening.		
20	MAPSHEET_GRID	NULL	VARCHAR2(3)
	The MAPSHEET GRID refers to NTG or BCGS grid. Values are 82, 83, 92, 93, 94, 95, 102, 103,104, 114.		
30	MAPSHEET_LETTER	NULL	VARCHAR2(1)
	The MAPSHEET LETTER is the NTG/BCGS letter. Values are A-P, and W.		
40	MAPSHEET_SQUARE	NULL	VARCHAR2(3)
	The MAPSHEET SQUARE represents BCGS number values between 1-100 or NTG Number values 1-16.		
50	MAPSHEET	NULL	VARCHAR2(7)
	The MAPSHEET is the full BCGS Mapsheet identifier. Eg. 92G100		
60	OPENING_NUMBER	NULL	VARCHAR2(4)
	The OPENING NUMBER is a unique four character field that is assigned to an opening on a specified mapsheet.		
61	MAP_LABEL	NULL	VARCHAR2(12)
	The default label to be used when displaying the feature on a map. Consists of the MAPSHEET GRID, MAPSHEET LETTER, MAPSHEET SQUARE, and OPENING NUMBER.		
70	OPENING_CATEGORY_CODE	NULL	VARCHAR2(7)
	The OPENING CATEGORY CODE indicates who holds the obligation and the extent and nature of the obligation. Eg. FTML - Forest Tenure Major Licensee; NDFS - Natural Disturbance Forest Service.		
80	OPENING_STATUS_CODE	NULL	VARCHAR2(3)
	The OPENING STATUS CODE indicates whether the opening is or is not free growing based on all standards units being declared free growing. It also is used to tracked specific pending administrative and legal processes. Eg. APP-Approved, FG-Free Growing; SUB-Submitted; AMD-Amending Silviculture Prescription.		
90	OPENING_LOCATION_NAME	NULL	VARCHAR2(30)
	The OPENING LOCATION NAME identifies the location name for the opening that is assigned by user. Eg. Peterson Creek.		
100	DISTRICT_ADMIN_ZONE	NULL	VARCHAR2(2)
	The DISTRICT ADMIN ZONE represents different administrative zones within the district. These District Admin Zones are created and managed by MOF district staff to assist with district work events.		
110	LICENSEE_OPENING_ID	NULL	VARCHAR2(30)
	The LICENSEE OPENING ID is a unique identifier provided by the Licensee to identify the Opening Number.		
120	MAX_ALLOW_PERMNT_ACCESS_PCT	NULL	NUMBER(3,1)
	The MAX ALLOW PERMNT ACCESS PCT is the maximum allowable permanent access percent is the total maximum percentage of the gross area of the opening that can be occupied by permanent access structures. Includes roads, landing, gravel pits, burrow pits, and permanent trails.		
130	APPROVE_DATE	NULL	DATE
	The APPROVAL DATE refers to the silviculture prescription approval date. For site plans, the approval date is auto-generated based on the first opening submission.		
140	TSB_NUMBER_CODE	NULL	VARCHAR2(3)
	The TSB NUMBER CODE is the Timber Supply Block that is manually assigned to the opening. For any tenured openings reference can be made using the Management Unit Code and ID.		
150	AMENDMENT_IND	NULL	VARCHAR2(1)
	The AMENDMENT IND indicates if there had been amendments made to the silviculture prescription or site plan on the opening. A value of 'Y' means there have been amendments. A value of 'N' means there have been no amendments.		
160	PREV_TREE_SPECIES1_CODE	NULL	VARCHAR2(8)
	The PREV TREE SPECIES1 CODE identifies the dominant species of the stand before harvest from the previous forest cover inventory label of the largest polygon in the opening.		
170	PREV_TREE_SPECIES2_CODE	NULL	VARCHAR2(8)
	The PREV TREE SPECIES2 CODE identifies the second species of the stand before harvest from the previous forest cover inventory label of the largest polygon in the opening.		

Table: RSLT_OPENING_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
180	PREV_STOCKING_STATUS_CODE	NULL	VARCHAR2(3)
	The PREV STOCKING STATUS CODE is obtained from the previous stand forest cover inventory label of the largest polygon in the opening.		
190	PREV_AGE_CLASS_CODE	NULL	VARCHAR2(1)
	The PREV AGE CLASS CODE is obtained from the previous stand forest cover inventory label of the largest polygon in the opening. Age classes are intervals, or ranges, or ages into which trees, forest, stands or forest types are classified.		
200	PREV_HEIGHT_CLASS_CODE	NULL	VARCHAR2(1)
	The PREV HEIGHT CLASS CODE is obtained from the previous stand forest cover inventory label of the largest polygon in the opening. Height classes represents intervals into range of trees or stand heights are classified.		
210	PREV_SITE_INDEX	NULL	NUMBER(5,0)
	The PREV SITE INDEX is obtained from the leading species of the previous stand forest cover inventory label of the largest polygon in the opening. Estimates forest land productivity.		
220	PREV_SITE_INDEX_SOURCE_CODE	NULL	VARCHAR2(1)
	The PREV SITE INDEX SOURCE CODE describes the source or origin of the previous site index obtained from the leading species of the previous stand forest cover inventory label of the largest polygon in the opening.		
230	RESULTS_SUBMISSION_ID	NULL	NUMBER(10,0)
	The RESULTS SUBMISSION ID is a system generated value generated by ESF to link between RESULTS opening data and the ESF submission.		
240	REGION_CODE	NULL	VARCHAR2(6)
	The REGION CODE is the MOFR Region Code that the opening is located in.		
250	REGION_NAME	NULL	VARCHAR2(100)
	The REGION NAME is the MOFR Region Name that the opening is located in.		
260	DISTRICT_CODE	NULL	VARCHAR2(6)
	The DISTRICT CODE is the MOFR District Code that the opening is located in.		
270	DISTRICT_NAME	NULL	VARCHAR2(100)
	The DISTRICT NAME is the MOFR District Name that the opening is located in.		
280	BCTS_CODE	NULL	VARCHAR2(6)
	The BCTS CODE is the BC Timber Sales Organizational Code that the BCTS opening is located in.		
290	BCTS_NAME	NULL	VARCHAR2(100)
	The BCTS NAME is the BC Timber Sales Organizational Name that the BCTS opening is located in.		
300	OPENING_GROSS_AREA	NULL	NUMBER(11,4)
	The OPENING GROSS AREA is the total area that the opening encompasses (e.g., 120 Hectares).		
310	FOREST_FILE_ID	NULL	VARCHAR2(10)
	The FOREST FILE ID represents the licence number of the opening corresponding to the cutting authority. Note where there is more than one tenure associated with the opening, the prime licence is shown. Eg. TFL49, A19204, W0014.		
320	CUTTING_PERMIT_ID	NULL	VARCHAR2(3)
	The CUTTING PERMIT ID is the cutting permit document number that corresponds to the licence associated with the opening. Note where there is more than one tenure associated with the opening, the prime licence is shown. Eg. TFL49, A19204, W0014.		
330	TIMBER_MARK	NULL	VARCHAR2(10)
	The TIMBER MARK is for the opening as shown on the legal document (eg. FT8675, 67801)		
340	CUT_BLOCK_ID	NULL	VARCHAR2(10)
	The CUT BLOCK ID is the approved cutblock identifier for the opening as the legal Exhibit 'A' document. Note where there is more than one tenure associated with the opening, the prime licence is shown. Eg. 1002LM		
350	MGMT_UNIT_ID	NULL	VARCHAR2(4)
	The MGMT UNIT ID the opening resides within. This is used in conjunction with Management Unit Type Code. This is auto-generated through tenure linkage based on the prime licence associated with the opening. Eg. U37-Strathcona TSA; T01-TFL01 Port Edward.		
360	MGMT_UNIT_TYPE_CODE	NULL	VARCHAR2(1)
	The MGMT UNIT TYPE CODE identifies the general type of administrative unit. This is often used with Management Unit Id to make reference to MOF administrative management unit. This is auto-generated through tenure linkage based on the prime licence associated with the opening. Eg. U-Timber Supply		

Table: RSLT_OPENING_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	Area; V-Timber Supply Block; T-Tree Farm Licence; F-Woodlot, etc.		
370	MGMT_UNIT_DESCRIPTION	NULL	VARCHAR2(100)
	The MGMT UNIT DESCRIPTION is the text reference to the specific administrative management unit based on opening's tenure linkage based on the prime licence. (eg. Kamloops TSA).		
380	FILE_TYPE_CODE	NULL	VARCHAR2(3)
	The FILE TYPE CODE is the tenure type associated with the licence. This is based on the opening's tenure prime licence. Eg. A01-Forest Licence; A02-Tree Farm Licence, etc.		
390	DISTURBANCE_START_DATE	NULL	DATE
	The DISTURBANCE START DATE is derived from the first reported disturbance activity reporting. This date is used to calculate the silviculture obligation milestones.		
400	DISTURBANCE_END_DATE	NULL	DATE
	The DISTURBANCE END DATE is derived from the last disturbance activity reporting record based on the disturbance activity's completion date.		
410	CLIENT_NAME	NULL	VARCHAR2(60)
	The CLIENT NAME in RESULTS refers to the opening's prime tenure and identifies the MOFR Client, Company or individual associated who owns the silviculture obligation.		
420	CLIENT_NUMBER	NULL	VARCHAR2(8)
	The Client Number is the Ministry's unique client number assigned to the Client Name. RESULTS refers the client information through the opening's prime tenure.		
430	CLIENT_LOCATION_CODE	NULL	VARCHAR2(2)
	The CLIENT LOCATION CODE is a further specific categorization code for those clients who may have more than one division.		
440	GENERALIZED_BGC_ZONE_CODE	NULL	VARCHAR2(4)
	The GENERALIZED BGC ZONE CODE is the Biogeoclimatic Ecosystem Classification (BEC) system. Eg. IDF; MS; CWH. This is derived from the largest standards unit for the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View.		
450	GENERALIZED_BGC_SUBZONE_CODE	NULL	VARCHAR2(3)
	The GENERALIZED BGC SUBZONE CODE is the Biogeoclimatic Ecosystem Classification (BEC) system. Eg. dk; xc; mk. This is derived from the largest standards unit for the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View.		
460	GENERALIZED_BGC_VARIANT	NULL	VARCHAR2(1)
	The GENERALIZED BGC VARIANT according to the BEC system. Eg. 1, 2. This is derived from the largest standards unit for the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View.		
470	GENERALIZED_BGC_PHASE	NULL	VARCHAR2(1)
	The GENERALIZED BGC PHASE according to the BEC system. This is derived from the largest standards units for the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View.		
480	GENERALIZED_BEC_SITE_SERIES	NULL	VARCHAR2(4)
	The GENERALIZED BEC SITE SERIES for the given biogeoclimatic unit, according to the BEC system. Eg. 01, 04, 05. This is derived from the largest standards unit for the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View		
490	GENERALIZED_BEC_SITE_TYPE	NULL	VARCHAR2(3)
	GENERALIZED BEC SITE TYPE for certain site series, according to the BEC system. This is derived from the largest standards unit from the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View.		
500	GENERALIZED_BEC_SERAL	NULL	VARCHAR2(4)
	GENERALIZED BEC SERIAL for certain site series, according to the BEC system. This is derived from the largest standards unit from the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View.		
510	DENUDATION_1_DISTURBANCE_CODE	NULL	VARCHAR2(3)
	The DENUDATION 1 DISTURBANCE CODE is based on the first disturbance activity reported, the disturbance code representing the disturbance origin. Eg. L-Logged, B-Burned, S-Salvage, etc.		
520	DENUDATION_1_SILV_SYSTEM_CODE	NULL	VARCHAR2(5)
	The DENUDATION 1 SILV SYSTEM CODE is based on the first disturbance activity reported, the silvicultural system used for the harvesting activity. Eg. CLEAR-Clearcut; CCRES-Clearcut with reserves; SELEC-Selection, etc.		

Table: RSLT_OPENING_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
530	DENUDATION_1_SILV_VARIANT_CODE	NULL	VARCHAR2(3)
	The DENUDATION 1 SILV VARIANT CODE is based on the first disturbance activity reported, the silvicultural system's variant which describes the distribution or removal pattern of the harvest. Eg. GRP-Group; IRR-Irregular; SIN-Single, etc.		
540	DENUDATION_1_CUT_PHASE_CODE	NULL	VARCHAR2(5)
	The DENUDATION 1 CUT PHASE CODE is based on the first disturbance activity reported, the silvicultural system's cut phase which describes the function of the harvest to extract merchantable timber and regeneration. Eg. GRP-Group; IRR-Irregular; SIN-Single, etc.		
550	DENUDATION_1_COMPLETION_DATE	NULL	DATE
	The DENUDATION 1 COMPLETION DATE is based on the first disturbance activity reported on the disturbance end date.		
560	DENUDATION_2_DISTURBANCE_CODE	NULL	VARCHAR2(3)
	The DENUDATION 2 DISTURBANCE CODE is based on the second disturbance activity reported, the disturbance code representing the disturbance origin. Eg. L-Logged, B-Burned, S-Salvage, etc.		
570	DENUDATION_2_SILV_SYSTEM_CODE	NULL	VARCHAR2(5)
	The DENUDATION 2 SILV SYSTEM CODE is based on the second disturbance activity reported, the silvicultural system used for the harvesting activity. Eg. CLEAR-Clearcut; CCRES-Clearcut with reserves; SELEC-Selection, etc.		
580	DENUDATION_2_SILV_VARIANT_CODE	NULL	VARCHAR2(3)
	The DENUDATION 2 SILV VARIANT CODE is based on the second disturbance activity reported, the silvicultural system's variant which describes the distribution or removal pattern of the harvest. Eg. GRP-Group; IRR-Irregular; SIN-Single, etc.		
590	DENUDATION_2_CUT_PHASE_CODE	NULL	VARCHAR2(5)
	The DENUDATION 2 CUT PHASE CODE is based on the second disturbance activity reported, the silvicultural system's cut phase which describes the function of the harvest to extract merchantable timber and regeneration. Eg. GRP-Group; IRR-Irregular; SIN-Single, etc.		
600	DENUDATION_2_COMPLETION_DATE	NULL	DATE
	The DENUDATION 2 COMPLETION DATE is based on the second disturbance activity reported on the disturbance end date.		
610	DENUDATION_COUNT	NULL	NUMBER(2,0)
	The DENUDATION COUNT is the total number of reported disturbance activities for the opening.		
620	SITE_PREP_1_TECHNIQUE_CODE	NULL	VARCHAR2(2)
	The SITE PREP 1 TECHNIQUE CODE is based on the first site preparation activity reported. The technique code describes the broad category used with site preparation activity (eg. BU Burn)		
630	SITE_PREP_1_TREATMENT_AREA	NULL	NUMBER(9,0)
	The SITE PREP 1 TREATMENT AREA is the total hectares reported for the first completed site preparation activity.		
640	SITE_PREP_1_COMPLETION_DATE	NULL	DATE
	The SITE PREP 1 COMPLETION DATE is the completion date of the first completed site preparation activity.		
650	SITE_PREP_2_TECHNIQUE_CODE	NULL	VARCHAR2(2)
	The SITE PREP 2 TECHNIQUE CODE is based on the second site preparation activity reported. The technique code describes the broad category used with site preparation activity (eg. BU Burn)		
660	SITE_PREP_2_TREATMENT_AREA	NULL	NUMBER(9,0)
	The SITE PREP 2 TREATMENT AREA is the total hectares reported for the second completed site preparation activity.		
670	SITE_PREP_2_COMPLETION_DATE	NULL	DATE
	The SITE PREP 2 COMPLETION DATE is the completion date of the second completed site preparation activity.		
680	SITE_PREP_COUNT	NULL	NUMBER(2,0)
	The SITE PREP COUNT is the total number of completed site preparation activities reported for the opening.		
690	PLANTING_1_TECHNIQUE_CODE	NULL	VARCHAR2(2)
	The PLANTING 1 TECHNIQUE CODE is based on the first planting activity reported. The technique code describes the broad category used with planting activity (eg. PL-Planting; RP-Replanting)		
700	PLANTING_1_TREATMENT_AREA	NULL	NUMBER(9,0)
	The PLANTING 1 TREATMENT AREA is the total hectares reported for the first completed planting		

Table: RSLT_OPENING_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	activity.		
710	PLANTING_1_COMPLETION_DATE	NULL	DATE
	The PLANTING 1 COMPLETION DATE is the completion date of the first completed planting activity.		
720	PLANTING_2_TECHNIQUE_CODE	NULL	VARCHAR2(2)
	The PLANTING 2 TECHNIQUE CODE is based on the second planting activity reported. The technique code describes the broad category used with planting activity (eg. PL-Planting; RP-Replanting)		
730	PLANTING_2_TREATMENT_AREA	NULL	NUMBER(9,0)
	The PLANTING 2 TREATMENT AREA is the total hectares reported for the second completed planting activity.		
740	PLANTING_2_COMPLETION_DATE	NULL	DATE
	The PLANTING 2 COMPLETION DATE is the completion date of the second completed planting activity.		
750	PLANTING_COUNT	NULL	NUMBER(2,0)
	The PLANTING COUNT is the total number of completed planting activity reported for the opening.		
760	BRUSHING_TECHNIQUE_CODE	NULL	VARCHAR2(2)
	The BRUSHING TECHNIQUE CODE is based on the first brushing activity reported. The technique code describes the broad category used with brushing activity (eg. MA-Manual; ME-Mechanical)		
770	BRUSHING_TREATMENT_AREA	NULL	NUMBER(9,0)
	The BRUSHING TREATMENT AREA is the total hectares reported for the first completed brushing activity.		
780	BRUSHING_COMPLETION_DATE	NULL	DATE
	The BRUSHING COMPLETION DATE is the completion date of the first completed brushing activity.		
790	BRUSHING_COUNT	NULL	NUMBER(2,0)
	The BRUSHING COUNT is the total number of completed brushing activity reported for the opening.		
800	SPACING_TREATMENT_AREA	NULL	NUMBER(9,0)
	The SPACING TREATMENT AREA is the total hectares reported for the first completed spacing activity.		
810	SPACING_COMPLETION_DATE	NULL	DATE
	The SPACING COMPLETION DATE is the completion date of the first completed spacing activity.		
820	SPACING_COUNT	NULL	NUMBER(2,0)
	The SPACING COUNT is the total number of completed spacing activity reported for the opening.		
830	FERTILIZATION_TREATMENT_AREA	NULL	NUMBER(9,0)
	The FERTILIZATION TREATMENT AREA is the total hectares reported for the first completed fertilization activity.		
840	FERTILIZATION_COMPLETION_DATE	NULL	DATE
	The FERTILIZATION COMPLETION DATE is the completion date of the first completed fertilization activity.		
850	FERTILIZATION_COUNT	NULL	NUMBER(2,0)
	The FERTILIZATION COUNT is the total number of completed fertilization activity reported for the opening.		
860	PRUNING_TREATMENT_AREA	NULL	NUMBER(9,0)
	The PRUNING TREATMENT AREA is the total hectares reported for the first completed pruning activity.		
870	PRUNING_COMPLETION_DATE	NULL	DATE
	The PRUNING COMPLETION DATE is the completion date of the first completed pruning activity.		
880	PRUNING_COUNT	NULL	NUMBER(2,0)
	The PRUNING COUNT is the total number of completed pruning activities reported for the opening.		
890	GEOMETRY_EXIST_IND	NULL	VARCHAR2(1)
	The GEOMETRY EXIST IND indicates if there is geometry for the opening. A value of 'Y' indicates there is geometry. A value of 'N' indicates there is no geometry.		
895	FEATURE_AREA	NULL	NUMBER(11,4)
	The FEATURE AREA is the area of the opening in square meters.		
900	FEATURE_PERIMETER	NULL	NUMBER(11,4)
	The FEATURE PERIMETER is the perimeter of the opening in meters.		
910	CAPTURE_METHOD_CODE	NULL	VARCHAR2(30)
	The CAPTURE METHOD CODE is a code defining the capture method. (e.g. digitize).		
920	DATA_SOURCE_CODE	NULL	VARCHAR2(10)
	The DATA SOURCE CODE is a code defining the source of the spatial feature (e.g. GPS, TRIM).		
930	OBSERVATION_DATE	NULL	DATE
	The OBSERVATION DATE is the geometry collection date.		
940	DATA_QUALITY_COMMENT	NULL	VARCHAR(255)

Table: RSLT_OPENING_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	The DATA QUALITY COMMENT is a comment indicating the Geometry accuracy.		
950	SUBMITTED_BY_USERID	NULL	VARCHAR2(30)
	The SUBMITTED BY USER ID is the USERID of the person who submitted the ESF information for the opening.		
960	SUBMITTED_DATE	NULL	DATE
	The SUBMITTED DATE is the date and time when ESF submitted for the opening.		
970	OPENING_WHO_CREATED	NOT NULL	VARCHAR2(30)
	The OPENING WHO CREATED is the USERID of the individual who created the opening record.		
980	OPENING_WHEN_CREATED	NOT NULL	DATE
	The OPENING WHEN CREATED is the date and time when the opening record was created.		
990	OPENING_WHO_UPDATED	NOT NULL	VARCHAR2(30)
	The OPENING WHO UPDATED is the USERID of the individual who last updated the opening record.		
1000	OPENING_WHEN_UPDATED	NOT NULL	DATE
	The OPENING WHEN UPDATED is the date and time when the opening record was last updated.		
1010	FEATURE_CLASS_SKEY	NULL	NUMBER(10,0)
	The FEATURE CLASS SKEY is the unique key assigned to a Feature Class by the Ministry of Forests.		
1020	GEOMETRY	NULL	
	The GEOMETRY is the opening geographical representation.		
1030	OBJECTID	NULL	NUMBER(10,0)
	The OBJECTID is a system generated value uniquely identifying the opening. Used by SDE.		

Table: RSLT_OPENING_VW

Description:

The administrative boundary of an area of land on which silviculture activities are planned and completed.

This view is intended to be joined with the other results view, providing addtional metadata to the Forest Cover, Activity and Silviculture data.

Columns:

Seq.	Column	Nulls?	Type
10	OPENING_ID	NOT NULL	NUMBER(10,0)
	The OPENING ID is a system generated value by RESULTS to uniquely identify the opening.		
20	MAPSHEET_GRID	NULL	VARCHAR2(3)
	The MAPSHEET GRID refers to NTG or BCGS grid. Values are 82, 83, 92, 93, 94, 95, 102, 103,104, 114.		
30	MAPSHEET_LETTER	NULL	VARCHAR2(1)
	The MAPSHEET LETTER is the NTG/BCGS letter. Values are A-P, and W.		
40	MAPSHEET_SQUARE	NULL	VARCHAR2(3)
	The MAPSHEET SQUARE represents BCGS number values between 1-100 or NTG Number values 1-16.		
50	MAPSHEET	NULL	VARCHAR2(7)
	The MAPSHEET is the full BCGS Mapsheet identifier. Eg. 92G100		
60	OPENING_NUMBER	NULL	VARCHAR2(4)
	The OPENING NUMBER is a unique four character field that is assigned to an opening on a specified mapsheet.		
70	OPENING_CATEGORY_CODE	NULL	VARCHAR2(7)
	The OPENING CATEGORY CODE indicates who holds the obligation and the extent and nature of the obligation. Eg. FTML - Forest Tenure Major Licensee; NDFS - Natural Disturbance Forest Service.		
80	OPENING_STATUS_CODE	NULL	VARCHAR2(3)
	The OPENING STATUS CODE indicates whether the opening is or is not free growing based on all standards units being declared free growing. It also is used to tracked specific pending administrative and legal processes. Eg. APP-Approved, FG-Free Growing; SUB-Submitted; AMD-Amending Silviculture Prescription.		
90	OPENING_LOCATION_NAME	NULL	VARCHAR2(30)
	The OPENING LOCATION NAME identifies the location name for the opening that is assigned by user. Eg. Peterson Creek.		
100	DISTRICT_ADMIN_ZONE	NULL	VARCHAR2(2)
	The DISTRICT ADMIN ZONE represents different administrative zones within the district. These District Admin Zones are created and managed by MOF district staff to assist with district work events.		
110	LICENSEE_OPENING_ID	NULL	VARCHAR2(30)
	The LICENSEE OPENING ID is a unique identifier provided by the Licensee to identify the Opening Number.		
120	MAX_ALLOW_PERMNT_ACCESS_PCT	NULL	NUMBER(3,1)
	The MAX ALLOW PERMNT ACCESS PCT is the maximum allowable permanent access percent is the total maximum percentage of the gross area of the opening that can be occupied by permanent access structures. Includes roads, landing, gravel pits, burrow pits, and permanent trails.		
130	APPROVE_DATE	NULL	DATE
	The APPROVAL DATE refers to the silviculture prescription approval date. For site plans, the approval date is auto-generated based on the first opening submission.		
140	TSB_NUMBER_CODE	NULL	VARCHAR2(3)
	The TSB NUMBER CODE is the Timber Supply Block that is manually assigned to the opening. For any tenured openings reference can be made using the Management Unit Code and ID.		
150	AMENDMENT_IND	NULL	VARCHAR2(1)
	The AMENDMENT IND indicates if there had been amendments made to the silviculture prescription or site plan on the opening. A value of 'Y' means there have been amendments. A value of 'N' means there have been no amendments.		
160	PREV_TREE_SPECIES1_CODE	NULL	VARCHAR2(8)
	The PREV TREE SPECIES1 CODE identifies the dominant species of the stand before harvest from the previous forest cover inventory label of the largest polygon in the opening.		
170	PREV_TREE_SPECIES2_CODE	NULL	VARCHAR2(8)
	The PREV TREE SPECIES2 CODE identifies the second species of the stand before harvest from the previous forest cover inventory label of the largest polygon in the opening.		
180	PREV_STOCKING_STATUS_CODE	NULL	VARCHAR2(3)

Table: RSLT_OPENING_VW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	The PREV STOCKING STATUS CODE is obtained from the previous stand forest cover inventory label of the largest polygon in the opening.		
190	PREV_AGE_CLASS_CODE	NULL	VARCHAR2(1)
	The PREV AGE CLASS CODE is obtained from the previous stand forest cover inventory label of the largest polygon in the opening. Age classes are intervals, or ranges, or ages into which trees, forest, stands or forest types are classified.		
200	PREV_HEIGHT_CLASS_CODE	NULL	VARCHAR2(1)
	The PREV HEIGHT CLASS CODE is obtained from the previous stand forest cover inventory label of the largest polygon in the opening. Height classes represents intervals into range of trees or stand heights are classified.		
210	PREV_SITE_INDEX	NULL	NUMBER(5,0)
	The PREV SITE INDEX is obtained from the leading species of the previous stand forest cover inventory label of the largest polygon in the opening. Estimates forest land productivity.		
220	PREV_SITE_INDEX_SOURCE_CODE	NULL	VARCHAR2(1)
	The PREV SITE INDEX SOURCE CODE describes the source or origin of the previous site index obtained from the leading species of the previous stand forest cover inventory label of the largest polygon in the opening.		
230	RESULTS_SUBMISSION_ID	NULL	NUMBER(10,0)
	The RESULTS SUBMISSION ID is a system generated value generated by ESF to link between RESULTS opening data and the ESF submission.		
240	REGION_CODE	NULL	VARCHAR2(6)
	The REGION CODE is the MOFR Region Code that the opening is located in.		
250	REGION_NAME	NULL	VARCHAR2(100)
	The REGION NAME is the MOFR Region Name that the opening is located in.		
260	DISTRICT_CODE	NULL	VARCHAR2(6)
	The DISTRICT CODE is the MOFR District Code that the opening is located in.		
270	DISTRICT_NAME	NULL	VARCHAR2(100)
	The DISTRICT NAME is the MOFR District Name that the opening is located in.		
280	BCTS_CODE	NULL	VARCHAR2(6)
	The BCTS CODE is the BC Timber Sales Organizational Code that the BCTS opening is located in.		
290	BCTS_NAME	NULL	VARCHAR2(100)
	The BCTS NAME is the BC Timber Sales Organizational Name that the BCTS opening is located in.		
300	OPENING_GROSS_AREA	NULL	NUMBER(11,4)
	The OPENING GROSS AREA is the total area that the opening encompasses (e.g., 120 Hectares).		
310	FOREST_FILE_ID	NULL	VARCHAR2(10)
	The FOREST FILE ID represents the licence number of the opening corresponding to the cutting authority. Note where there is more than one tenure associated with the opening, the prime licence is shown. Eg. TFL49, A19204, W0014.		
320	CUTTING_PERMIT_ID	NULL	VARCHAR2(3)
	The CUTTING PERMIT ID is the cutting permit document number that corresponds to the licence associated with the opening. Note where there is more than one tenure associated with the opening, the prime licence is shown. Eg. TFL49, A19204, W0014.		
330	TIMBER_MARK	NULL	VARCHAR2(10)
	The TIMBER MARK is for the opening as shown on the legal document (eg. FT8675, 67801)		
340	CUT_BLOCK_ID	NULL	VARCHAR2(10)
	The CUT BLOCK ID is the approved cutblock identifier for the opening as the legal Exhibit 'A' document. Note where there is more than one tenure associated with the opening, the prime licence is shown. Eg. 1002LM		
350	MGMT_UNIT_ID	NULL	VARCHAR2(4)
	The MGMT UNIT ID the opening resides within. This is used in conjunction with Management Unit Type Code. This is auto-generated through tenure linkage based on the prime licence associated with the opening. Eg. U37-Strathcona TSA; T01-TFL01 Port Edward.		
360	MGMT_UNIT_TYPE_CODE	NULL	VARCHAR2(1)
	The MGMT UNIT TYPE CODE identifies the general type of administrative unit. This is often used with Management Unit Id to make reference to MOF administrative management unit. This is auto-generated through tenure linkage based on the prime licence associated with the opening. Eg. U-Timber Supply Area; V-Timber Supply Block; T-Tree Farm Licence; F-Woodlot, etc.		

Table: RSLT_OPENING_VW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
370	MGMT_UNIT_DESCRIPTION	NULL	VARCHAR2(100)
	The MGMT UNIT DESCRIPTION is the text reference to the specific administrative management unit based on opening's tenure linkage based on the prime licence. (eg. Kamloops TSA).		
380	FILE_TYPE_CODE	NULL	VARCHAR2(3)
	The FILE TYPE CODE is the tenure type associated with the licence. This is based on the opening's tenure prime licence. Eg. A01-Forest Licence; A02-Tree Farm Licence, etc.		
390	DISTURBANCE_START_DATE	NULL	DATE
	The DISTURBANCE START DATE is derived from the first reported disturbance activity reporting. This date is used to calculate the silviculture obligation milestones.		
400	DISTURBANCE_END_DATE	NULL	DATE
	The DISTURBANCE END DATE is derived from the last disturbance activity reporting record based on the disturbance activity's completion date.		
410	CLIENT_NAME	NULL	VARCHAR2(60)
	The CLIENT NAME in RESULTS refers to the opening's prime tenure and identifies the MOFR Client, Company or individual associated who owns the silviculture obligation.		
420	CLIENT_NUMBER	NULL	VARCHAR2(8)
	The Client Number is the Ministry's unique client number assigned to the Client Name. RESULTS refers the client information through the opening's prime tenure.		
430	CLIENT_LOCATION_CODE	NULL	VARCHAR2(2)
	The CLIENT LOCATION CODE is a further specific categorization code for those clients who may have more than one division.		
440	GENERALIZED_BGC_ZONE_CODE	NULL	VARCHAR2(4)
	The GENERALIZED BGC ZONE CODE is the Biogeoclimatic Ecosystem Classification (BEC) system. Eg. IDF; MS; CWH. This is derived from the largest standards unit for the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View.		
450	GENERALIZED_BGC_SUBZONE_CODE	NULL	VARCHAR2(3)
	The GENERALIZED BGC SUBZONE CODE is the Biogeoclimatic Ecosystem Classification (BEC) system. Eg. dk; xc; mk. This is derived from the largest standards unit for the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View.		
460	GENERALIZED_BGC_VARIANT	NULL	VARCHAR2(1)
	The GENERALIZED BGC VARIANT according to the BEC system. Eg. 1, 2. This is derived from the largest standards unit for the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View.		
470	GENERALIZED_BGC_PHASE	NULL	VARCHAR2(1)
	The GENERALIZED BGC PHASE according to the BEC system. This is derived from the largest standards units for the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View.		
480	GENERALIZED_BEC_SITE_SERIES	NULL	VARCHAR2(4)
	The GENERALIZED BEC SITE SERIES for the given biogeoclimatic unit, according to the BEC system. Eg. 01, 04, 05. This is derived from the largest standards unit for the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View		
490	GENERALIZED_BEC_SITE_TYPE	NULL	VARCHAR2(3)
	GENERALIZED BEC SITE TYPE for certain site series, according to the BEC system. This is derived from the largest standards unit from the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View.		
500	GENERALIZED_BEC_SERAL	NULL	VARCHAR2(4)
	GENERALIZED BEC SERIAL for certain site series, according to the BEC system. This is derived from the largest standards unit from the opening and applied to the opening. Detailed source data can be obtained through the Standards Unit View.		
510	DENUDATION_1_DISTURBANCE_CODE	NULL	VARCHAR2(3)
	The DENUDATION 1 DISTURBANCE CODE is based on the first disturbance activity reported, the disturbance code representing the disturbance origin. Eg. L-Logged, B-Burned, S-Salvage, etc.		
520	DENUDATION_1_SILV_SYSTEM_CODE	NULL	VARCHAR2(5)
	The DENUDATION 1 SILV SYSTEM CODE is based on the first disturbance activity reported, the silvicultural system used for the harvesting activity. Eg. CLEAR-Clearcut; CCRES-Clearcut with reserves; SELEC-Selection, etc.		
530	DENUDATION_1_SILV_VARIANT_CODE	NULL	VARCHAR2(3)

Table: RSLT_OPENING_VW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	The DENUDATION 1 SILV VARIANT CODE is based on the first disturbance activity reported, the silvicultural system's variant which describes the distribution or removal pattern of the harvest. Eg. GRP-Group; IRR-Irregular; SIN-Single, etc.		
540	DENUDATION_1_CUT_PHASE_CODE	NULL	VARCHAR2(5)
	The DENUDATION 1 CUT PHASE CODE is based on the first disturbance activity reported, the silvicultural system's cut phase which describes the function of the harvest to extract merchantable timber and regeneration. Eg. GRP-Group; IRR-Irregular; SIN-Single, etc.		
550	DENUDATION_1_COMPLETION_DATE	NULL	DATE
	The DENUDATION 1 COMPLETION DATE is based on the first disturbance activity reported on the disturbance end date.		
560	DENUDATION_2_DISTURBANCE_CODE	NULL	VARCHAR2(3)
	The DENUDATION 2 DISTURBANCE CODE is based on the second disturbance activity reported, the disturbance code representing the disturbance origin. Eg. L-Logged, B-Burned, S-Salvage, etc.		
570	DENUDATION_2_SILV_SYSTEM_CODE	NULL	VARCHAR2(5)
	The DENUDATION 2 SILV SYSTEM CODE is based on the second disturbance activity reported, the silvicultural system used for the harvesting activity. Eg. CLEAR-Clearcut; CCRES-Clearcut with reserves; SELEC-Selection, etc.		
580	DENUDATION_2_SILV_VARIANT_CODE	NULL	VARCHAR2(3)
	The DENUDATION 2 SILV VARIANT CODE is based on the second disturbance activity reported, the silvicultural system's variant which describes the distribution or removal pattern of the harvest. Eg. GRP-Group; IRR-Irregular; SIN-Single, etc.		
590	DENUDATION_2_CUT_PHASE_CODE	NULL	VARCHAR2(5)
	The DENUDATION 2 CUT PHASE CODE is based on the second disturbance activity reported, the silvicultural system's cut phase which describes the function of the harvest to extract merchantable timber and regeneration. Eg. GRP-Group; IRR-Irregular; SIN-Single, etc.		
600	DENUDATION_2_COMPLETION_DATE	NULL	DATE
	The DENUDATION 2 COMPLETION DATE is based on the second disturbance activity reported on the disturbance end date.		
610	DENUDATION_COUNT	NULL	NUMBER(2,0)
	The DENUDATION COUNT is the total number of reported disturbance activities for the opening.		
620	SITE_PREP_1_TECHNIQUE_CODE	NULL	VARCHAR2(2)
	The SITE PREP 1 TECHNIQUE CODE is based on the first site preparation activity reported. The technique code describes the broad category used with site preparation activity (eg. BU Burn)		
630	SITE_PREP_1_TREATMENT_AREA	NULL	NUMBER(9,0)
	The SITE PREP 1 TREATMENT AREA is the total hectares reported for the first completed site preparation activity.		
640	SITE_PREP_1_COMPLETION_DATE	NULL	DATE
	The SITE PREP 1 COMPLETION DATE is the completion date of the first completed site preparation activity.		
650	SITE_PREP_2_TECHNIQUE_CODE	NULL	VARCHAR2(2)
	The SITE PREP 2 TECHNIQUE CODE is based on the second site preparation activity reported. The technique code describes the broad category used with site preparation activity (eg. BU Burn)		
660	SITE_PREP_2_TREATMENT_AREA	NULL	NUMBER(9,0)
	The SITE PREP 2 TREATMENT AREA is the total hectares reported for the second completed site preparation activity.		
670	SITE_PREP_2_COMPLETION_DATE	NULL	DATE
	The SITE PREP 2 COMPLETION DATE is the completion date of the second completed site preparation activity.		
680	SITE_PREP_COUNT	NULL	NUMBER(2,0)
	The SITE PREP COUNT is the total number of completed site preparation activities reported for the opening.		
690	PLANTING_1_TECHNIQUE_CODE	NULL	VARCHAR2(2)
	The PLANTING 1 TECHNIQUE CODE is based on the first planting activity reported. The technique code describes the broad category used with planting activity (eg. PL-Planting; RP-Replanting)		
700	PLANTING_1_TREATMENT_AREA	NULL	NUMBER(9,0)
	The PLANTING 1 TREATMENT AREA is the total hectares reported for the first completed planting activity.		

Table: RSLT_OPENING_VW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
710	PLANTING_1_COMPLETION_DATE	NULL	DATE
	The PLANTING 1 COMPLETION DATE is the completion date of the first completed planting activity.		
720	PLANTING_2_TECHNIQUE_CODE	NULL	VARCHAR2(2)
	The PLANTING 2 TECHNIQUE CODE is based on the second planting activity reported. The technique code describes the broad category used with planting activity (eg. PL-Planting; RP-Replanting)		
730	PLANTING_2_TREATMENT_AREA	NULL	NUMBER(9,0)
	The PLANTING 2 TREATMENT AREA is the total hectares reported for the second completed planting activity.		
740	PLANTING_2_COMPLETION_DATE	NULL	DATE
	The PLANTING 2 COMPLETION DATE is the completion date of the second completed planting activity.		
750	PLANTING_COUNT	NULL	NUMBER(2,0)
	The PLANTING COUNT is the total number of completed planting activity reported for the opening.		
760	BRUSHING_TECHNIQUE_CODE	NULL	VARCHAR2(2)
	The BRUSHING TECHNIQUE CODE is based on the first brushing activity reported. The technique code describes the broad category used with brushing activity (eg. MA-Manual; ME-Mechanical)		
770	BRUSHING_TREATMENT_AREA	NULL	NUMBER(9,0)
	The BRUSHING TREATMENT AREA is the total hectares reported for the first completed brushing activity.		
780	BRUSHING_COMPLETION_DATE	NULL	DATE
	The BRUSHING COMPLETION DATE is the completion date of the first completed brushing activity.		
790	BRUSHING_COUNT	NULL	NUMBER(2,0)
	The BRUSHING COUNT is the total number of completed brushing activity reported for the opening.		
800	SPACING_TREATMENT_AREA	NULL	NUMBER(9,0)
	The SPACING TREATMENT AREA is the total hectares reported for the first completed spacing activity.		
810	SPACING_COMPLETION_DATE	NULL	DATE
	The SPACING COMPLETION DATE is the completion date of the first completed spacing activity.		
820	SPACING_COUNT	NULL	NUMBER(2,0)
	The SPACING COUNT is the total number of completed spacing activity reported for the opening.		
830	FERTILIZATION_TREATMENT_AREA	NULL	NUMBER(9,0)
	The FERTILIZATION TREATMENT AREA is the total hectares reported for the first completed fertilization activity.		
840	FERTILIZATION_COMPLETION_DATE	NULL	DATE
	The FERTILIZATION COMPLETION DATE is the completion date of the first completed fertilization activity.		
850	FERTILIZATION_COUNT	NULL	NUMBER(2,0)
	The FERTILIZATION COUNT is the total number of completed fertilization activity reported for the opening.		
860	PRUNING_TREATMENT_AREA	NULL	NUMBER(9,0)
	The PRUNING TREATMENT AREA is the total hectares reported for the first completed pruning activity.		
870	PRUNING_COMPLETION_DATE	NULL	DATE
	The PRUNING COMPLETION DATE is the completion date of the first completed pruning activity.		
880	PRUNING_COUNT	NULL	NUMBER(2,0)
	The PRUNING COUNT is the total number of completed pruning activities reported for the opening.		
890	SUBMITTED_BY_USERID	NULL	VARCHAR2(30)
	The SUBMITTED BY USER ID is the USERID of the person who submitted the ESF information for the opening.		
900	SUBMITTED_DATE	NULL	DATE
	The SUBMITTED DATE is the date and time when ESF submitted for the opening.		
910	OPENING_WHO_CREATED	NOT NULL	VARCHAR2(30)
	The OPENING WHO CREATED is the USERID of the individual who created the opening record.		
920	OPENING_WHEN_CREATED	NOT NULL	DATE
	The OPENING WHEN CREATED is the date and time when the opening record was created.		
930	OPENING_WHO_UPDATED	NOT NULL	VARCHAR2(30)
	The OPENING WHO UPDATED is the USERID of the individual who last updated the opening record.		
940	OPENING_WHEN_UPDATED	NOT NULL	DATE
	The OPENING WHEN UPDATED is the date and time when the opening record was last updated.		

Notes:

Table: RSLT_OPENING_VW (cont'd)

Notes:

The administration boundary representing an area that had been harvested or disturbed where there are forest management activities. This view contains all of the same attribute information as the RSLT_OPENING_SVW view, but not the spatial information. This view is intended to be used to join to other RESULTS views (eg RSLT_FOREST_COVER_INV_SVW) to provide information about the Opening when the Opening spatial information is not needed.

Table: RSLT_PLANTING_POLY

Description:

The spatial representation for a planting activity that occurs within an opening. Specific information about the planting activity, including the tree species planted and the where the trees were sourced from (seedlot or veg lot) are included.

Columns:

Seq.	Column	Nulls?	Type
* 10	ACTIVITY_TREATMENT_UNIT_ID	NOT NULL	NUMBER(10,0)
	The ACTIVITY TREATMENT UNIT ID is a system generated value by RESULTS to uniquely identify the disturbance or silviculture activity.		
20	ACTIVITY_LICENSEE_ID	NULL	VARCHAR2(30)
	The ACTIVITY LICENSEE ID is a unique identifier provided by the Licensee or submitter to identify the disturbance or silviculture activity. Ex. 160699058.		
30	OPENING_ID	NOT NULL	NUMBER(10,0)
	The OPENING ID is a system generated value by RESULTS to uniquely identify the opening.		
35	MAP_LABEL	NOT NULL	VARCHAR2(55)
	The default label to be used when displaying the feature on a map. Consists of the SILV TREE SPECIES CODE, NUMBER PLANTED, and ATU COMPLETION DATE.		
40	SILV_BASE_CODE	NOT NULL	VARCHAR2(2)
	The SILV BASE CODE identifies primary category of the completed planting activity: PL-Planting		
50	SILV_TECHNIQUE_CODE	NULL	VARCHAR2(2)
	The SILV TECHNIQUE CODE describes the broad category of technique associated with the completed planting activity (eg. PL-Planting, FP-Fill Planting; RP-Replanting)		
60	SILV_METHOD_CODE	NULL	VARCHAR2(5)
	The SILV METHOD CODE describes the specific machinery or method used for the planned silviculture activity base/technique combination (eg. Planting/Planting/Containert: Base Code-PL Technique Code-PL Method Code -CTAIN)		
70	SILV_OBJECTIVE_CODE_1	NULL	VARCHAR2(3)
	The SILV OBJECTIVE CODE 1 describes an objective for performing the completed planting activity. There may be up to three objectives for each planting activity.		
80	SILV_OBJECTIVE_CODE_2	NULL	VARCHAR2(3)
	The SILV OBJECTIVE CODE 2 describes an objective for performing the completed planting activity. There may be up to three objectives for each planting activity.		
90	SILV_OBJECTIVE_CODE_3	NULL	VARCHAR2(3)
	The SILV OBJECTIVE CODE 3 describes an objective for performing the completed planting activity. There may be up to three objectives for each planting activity.		
100	SILV_FUND_SOURCE_CODE	NULL	VARCHAR2(3)
	The SILV FUND SOURCE CODE describes the actual funding source for the completed planting activity on the opening. Example: FID-Forest Investment Account - FRPA 108.		
110	ATU_COMPLETION_DATE	NULL	DATE
	The ATU COMPLETION DATE is the planting completion date for the activity treatment unit (ATU).		
120	ACTUAL_TREATMENT_AREA	NULL	NUMBER(11,1)
	The ACTUAL TREATMENT AREA is the completed amount (based on reported unit of measure) for the planting activity in hectares.		
130	ACTUAL_TREATMENT_COST	NULL	NUMBER(9,0)
	The ACTUAL TREATMENT COST is the cost for the completed planted treatment.		
150	SILVICULTURE_PROJECT_ID	NULL	VARCHAR2(13)
	The SILVICULTURE PROJECT ID is a RESULTS system-generated unique identifier is assigned to an activity which identified a unit within a RESULTS's project. *TPM 2008-08-06 Updated the column type to be VARCHAR2(13).*		
160	FIA_PROJECT_ID	NULL	VARCHAR2(10)
	The FIA PROJECT ID is a unique identifier provided by submitter that links to other agencies' databases "Inter-agency Number". Example: 4237006.		
* 170	PLANTING_RESULTS_SEQ_NUMBER	NOT NULL	NUMBER(5,0)
	The PLANTING RESULTS SEQ NUMBER is a system-generated number to order the species reported into RESULTS for the planting activity		
180	SILV_TREE_SPECIES_CODE	NOT NULL	VARCHAR2(8)
	The SILV TREE SPECIES CODE is the tree species for the completed planting activity for the seedlot/veglot. Note that each species seedlot/veglot is reported separately. Example: CW-WESTERN RED CEDAR;SW-WHITE SPRUCE; etc.		

Table: RSLT_PLANTING_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
190	NUMBER_PLANTED	NULL	NUMBER(10,0)
	The NUMBER PLANTED is the number of trees planted for the tree species seedlot/veglot for the planted activity. Note that each species seedlot/veglot is reported separately.		
200	PLANTED_NO_BEYOND_XFER_LIMIT	NULL	NUMBER(10)
	The PLANTED NO BEYOND XFER LIMIT is the number of trees planted beyond the seed transfer limit guidelines for the species seedlot/veglot for the activity.		
210	SEEDLOT_NUMBER	NULL	VARCHAR2(5)
	The SEEDLOT NUMBER is the unique number (key) assigned by SPAR to seed source and quality collected at a given time and location. Example: 00524.		
220	VEG_LOT_ID	NULL	VARCHAR2(5)
	The VEG LOT ID is the unique number (key) assigned by SPAR to vegetative cutting collected at a given time and location. Example: V0049.		
230	REQUEST_SKEY	NULL	NUMBER(10)
	The REQUEST ID is a unique planting request number form SPAR which indicates the ordered seedlings. This field is optional.		
240	GENETIC_CLASS_CODE	NULL	VARCHAR2(1)
	The GENETIC CLASS CODE is a code which represents the genetic quality of material (seed or cuttings). 'A' class represents superior orchard produced seed or cuttings. 'B' class represents naturally collected seed or cuttings.		
250	SUPERIOR_PROVIDENCE_IND	NULL	VARCHAR2(1)
	The SUPERIOR PROVIDENCE IND is an indicator identifying whether the material originated from a superior provenance ('Y' - yes) or not ('N' - No).		
260	REGISTERED_SEED_IND	NULL	VARCHAR2(1)
	The REGISTERED SEED IND is an indicator which represents whether a seed lot is registered for crown land reforestation use ('Y' yes) or not ('N' no).		
710	GEOMETRY_EXIST_IND	NULL	VARCHAR2(1)
	The GEOMETRY EXIST IND indicates if there is geometry for the opening. A value of 'Y' indicates there is geometry. A value of 'N' indicates there is no geometry.		
720	FEATURE_AREA	NULL	NUMBER(11,4)
	The FEATURE AREA is the area of the feature in square meters.		
730	FEATURE_PERIMETER	NULL	NUMBER(11,4)
	The FEATURE PERIMETER is the perimeter of the feature in meters.		
740	CAPTURE_METHOD_CODE	NULL	VARCHAR2(30)
	The CAPTURE METHOD CODE is a code defining the capture method. (e.g. digitize).		
750	DATA_SOURCE_CODE	NULL	VARCHAR2(10)
	The DATA SOURCE CODE is a code defining the source of the spatial feature (e.g. GPS, TRIM).		
760	OBSERVATION_DATE	NULL	DATE
	The OBSERVATION DATE is the geometry collection date.		
770	DATA_QUALITY_COMMENT	NULL	VARCHAR2(255)
	The DATA QUALITY COMMENT is a comment indicating the Geometry accuracy.		
780	ATU_WHO_CREATED	NOT NULL	VARCHAR2(30)
	The ATU WHO CREATED is the USERID of the individual who created the activity record.		
790	ATU_WHEN_CREATED	NOT NULL	DATE
	The ATU WHO UPDATED is the date and time when the activity record was created.		
800	ATU_WHO_UPDATED	NOT NULL	VARCHAR2(30)
	The ATU WHEN UPDATED is the USERID of the individual who last updated the activity record.		
810	ATU_WHEN_UPDATED	NOT NULL	DATE
	THE ATU WHEN UPDATED is the date and time when the activity record was last updated.		
820	CHANGE_TIMESTAMP1	NOT NULL	DATE
	The date and time of the last update to the ACTIVITY TREATMENT UNIT table.		
830	CHANGE_TIMESTAMP2	NULL	DATE
	The date and time of the last update to the ACTIVITY TREATMENT GEOMETRY table.		
1060	CHANGE_TIMESTAMP3	NOT NULL	DATE
	The date and time of the last update to the PLANTING RSLT table.		
1070	CHANGE_TIMESTAMP4	NULL	DATE
	The date and time of the last update to the SEEDLOT table.		

Table: RSLT_PLANTING_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
1080	FEATURE_CLASS_SKEY	NULL	NUMBER(10,0)
	The FEATURE CLASS SKEY is the unique key assigned to a Feature Class by the Ministry of Forests.		
1090	GEOMETRY	NULL	
	The GEOMETRY is the Activity Treatment Unit geographical representation.		
4321	OBJECTID	NOT NULL	INTEGER
	The OBJECTID is a system generated value uniquely identifying the opening. Used by SDE.		

Unique Constraints:

RSLT_PLT_UK
OBJECTID

Foreign Keys:

RSLT_PLT_RSLT_OPEN_FK
OPENING_ID = RSLT_OPENING_POLYGON.OPENING_ID

Indexes:

RSLT_PLT_GEOM_I
GEOMETRY
RSLT_PLT_RSLT_OPEN_FK_I
OPENING_ID

Table: RSLT_PLANTING_SVW

Description:

The spatial representation for a planting activity that occurs within an opening. Specific information about the planting activity, including the tree species planted and the where the trees were sourced from (seedlot or veg lot) are included.

Columns:

Seq.	Column	Nulls?	Type
10	ACTIVITY_TREATMENT_UNIT_ID	NOT NULL	NUMBER(10,0)
	The ACTIVITY TREATMENT UNIT ID is a system generated value by RESULTS to uniquely identify the disturbance or silviculture activity.		
20	ACTIVITY_LICENSEE_ID	NULL	VARCHAR2(30)
	The ACTIVITY LICENSEE ID is a unique identifier provided by the Licensee or submitter to identify the disturbance or silviculture activity.		
30	OPENING_ID	NOT NULL	NUMBER(10,0)
	The OPENING ID is a system generated value by RESULTS to uniquely identify the opening.		
32	MAP_LABEL	NOT NULL	VARCHAR2(55)
	The default label to be used when displaying the feature on a map. Consists of the SILV TREE SPECIES CODE, NUMBER PLANTED, and ATU COMPLETION DATE.		
35	SILV_BASE_CODE	NULL	VARCHAR2(2)
	The SILV BASE CODE identifies primary category of the completed planting activity: PL-Planting		
50	SILV_TECHNIQUE_CODE	NULL	VARCHAR2(2)
	The SILV TECHNIQUE CODE describes the broad category of technique associated with the completed planting activity (eg. PL-Planting, FP-Fill Planting; RP-Replanting)		
60	SILV_METHOD_CODE	NULL	VARCHAR2(5)
	The SILV METHOD CODE describes the specific machinery or method used for the planned silviculture activity base/technique combination (eg. Planting/Planting/Containert: Base Code-PL Technique Code-PL Method Code -CTAIN)		
70	SILV_OBJECTIVE_CODE_1	NULL	VARCHAR2(3)
	The SILV OBJECTIVE CODE 1 describes the objective for performing the completed planting activity.		
80	SILV_OBJECTIVE_CODE_2	NULL	VARCHAR2(3)
	The SILV OBJECTIVE CODE 2 describes the objective for performing the completed planting activity.		
90	SILV_OBJECTIVE_CODE_3	NULL	VARCHAR2(3)
	The SILV OBJECTIVE CODE 3 describes the objective for performing the completed planting activity.		
100	SILV_FUND_SOURCE_CODE	NULL	VARCHAR2(3)
	The SILV FUND SOURCE CODE describes the actual funding source for the completed planting activity on the opening.		
110	ATU_COMPLETION_DATE	NULL	DATE
	The ATU COMPLETION DATE is the planting completion date for the activity.		
120	ACTUAL_TREATMENT_AREA	NULL	NUMBER(11,1)
	The ACTUAL TREATMENT AREA is the completed amount (based on reported unit of measure) for the planting activity in hectares.		
130	ACTUAL_TREATMENT_COST	NULL	NUMBER(9,0)
	The ACTUAL TREATMENT COST is the cost for the completed planted treatment.		
140	SILVICULTURE_PROJECT_ID	NULL	NUMBER(10,0)
	The SILVICULTURE PROJECT ID is a RESULTS system-generated unique identifier is assigned to an activity which identified a unit within a RESULTS's project.		
150	FIA_PROJECT_ID	NULL	VARCHAR2(10)
	The FIA PROJECT ID is a unique identifier provided by submitter that links to other agencies' databases "Inter-agency Number".		
160	PLANTING_RESULTS_SEQ_NUMBER	NOT NULL	NUMBER(5,0)
	The PLANTING RESULTS SEQ NUMBER is a system-generated number to order the species reported into RESULTS for the planting activity		
170	SILV_TREE_SPECIES_CODE	NULL	VARCHAR2(8)
	The SILV TREE SPECIES CODE is the tree species for the completed planting activity for the seedlot/veglot. Note that each species seedlot/veglot is reported separately.		
180	NUMBER_PLANTED	NULL	NUMBER(10,0)
	The NUMBER PLANTED is the number of trees planted for the tree species seedlot/veglot for the planted activity. Note that each species seedlot/veglot is reported separately.		
190	PLANTED_NO_BEYOND_XFER_LIMIT	NULL	NUMBER(10)
	The PLANTED NO BEYOND XFER LIMIT is the number of trees planted beyond the seed transfer limit		

Table: RSLT_PLANTING_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	guidelines for the species seedlot/veglot for the activity.		
200	SEEDLOT_NUMBER	NULL	VARCHAR2(5)
	The SEEDLOT NUMBER is the unique number (key) assigned by SPAR to seed source and quality collected at a given time and location.		
210	VEG_LOT_ID	NULL	VARCHAR2(5)
	The VEG LOT ID is the unique number (key) assigned by SPAR to vegetative cutting collected at a given time and location.		
220	REQUEST_SKEY	NULL	NUMBER(10)
	The REQUEST ID is a unique planting request number form SPAR which indicates the ordered seedlings. This field is optional.		
230	GENETIC_CLASS_CODE	NULL	VARCHAR2(1)
	The GENETIC CLASS CODE is a code which represents the genetic quality of material (seed or cuttings). 'A' class represents superior orchard produced seed or cuttings. 'B' class represents naturally collected seed or cuttings.		
240	SUPERIOR_PROVIDENCE_IND	NULL	VARCHAR2(1)
	The SUPERIOR PROVIDENCE IND is an indicator identifying whether the material originated from a superior provenance ('Y' - yes) or not ('N' - No).		
250	REGISTERED_SEED_IND	NULL	VARCHAR2(1)
	The REGISTERED SEED IND is an indicator which represents whether a seed lot is registered for crown land reforestation use ('Y' yes) or not ('N' no).		
260	GEOMETRY_EXIST_IND	NULL	VARCHAR2(1)
	The GEOMETRY EXIST IND indicates if there is geometry for the opening. A value of 'Y' indicates there is geometry. A value of 'N' indicates there is no geometry.		
265	FEATURE_AREA	NULL	NUMBER(11,4)
	The FEATURE AREA is the area of the feature in square meters.		
270	FEATURE_PERIMETER	NULL	NUMBER(11,4)
	The FEATURE PERIMETER is the perimeter of the feature in meters.		
280	CAPTURE_METHOD_CODE	NULL	VARCHAR2(30)
	The CAPTURE METHOD CODE is a code defining the capture method. (e.g. digitize).		
290	DATA_SOURCE_CODE	NULL	VARCHAR2(10)
	The FEATURE CLASS SKEY is the unique key assigned to a Feature Class by the Ministry of Forests.		
300	OBSERVATION_DATE	NULL	DATE
	The OBSERVATION DATE is the geometry collection date.		
310	DATA_QUALITY_COMMENT	NULL	VARCHAR2(255)
	The DATA QUALITY COMMENT is a comment indicating the Geometry accuracy.		
320	ATU_WHO_CREATED	NOT NULL	VARCHAR2(30)
	The ATU WHO CREATED is the USERID of the individual who created the activity record.		
330	ATU_WHEN_CREATED	NOT NULL	DATE
	The ATU WHO UPDATED is the date and time when the activity record was created.		
340	ATU_WHO_UPDATED	NOT NULL	VARCHAR2(30)
	The ATU WHEN UPDATED is the USERID of the individual who last updated the activity record.		
350	ATU_WHEN_UPDATED	NOT NULL	DATE
	THE ATU WHEN UPDATED is the date and time when the activity record was last updated.		
360	FEATURE_CLASS_SKEY	NULL	NUMBER(10,0)
	The DATA SOURCE CODE is a code defining the source of the spatial feature (e.g. GPS, TRIM).		
370	GEOMETRY	NULL	
	The GEOMETRY is the Activity Treatment Unit geographical representation.		
390	OBJECTID	NOT NULL	NUMBER(10,0)
	The OBJECTID is a system generated value uniquely identifying the opening. Used by SDE.		

Table: RSLT_STANDARDS_UNIT_POLY

Description:

The spatial representation for a stocking standard, which is a basic Silviculture objective stated in quantifiable terms for a specific area. These are the acceptable standards for reforestation and soil conversation. Also known as SU - Standards Unit.

Columns:

Seq.	Column	Nulls?	Type
* 10	STOCKING_STANDARD_UNIT_ID	NOT NULL	NUMBER(10,0)
	The STOCKING STANDARD UNIT ID is a system-generated value by RESULTS to uniquely identify standards units.		
20	STANDARDS_UNIT_ID	NOT NULL	VARCHAR2(4)
	The STANDARDS UNIT ID is an assigned unique identifier that represents the standards units which is apart of a opening for which one or parts were there is similar soil disturbance, regeneration and free growing dates, stocking standards and free growing height that contributes to the establishing free growing stand on the opening. Ex SU1.		
30	STANDARDS_REGIME_ID	NULL	NUMBER(10,0)
	The STANDARDS REGIME ID is that assigned unique identifier representing an approved stocking standard applied to the Standards Unit.		
40	OPENING_ID	NOT NULL	NUMBER(10,0)
	The OPENING ID is a system generated value by RESULTS to uniquely identify the opening.		
45	MAP_LABEL	NOT NULL	VARCHAR2(4)
	The default label to be used when displaying the feature on a map. Consists of the STANDARDS UNIT ID.		
50	NET_AREA	NOT NULL	NUMBER(7,1)
	This NET AREA is the net area (in hectares) of the Standards Unit (ie. does not include roads, reserves, non-productive areas).		
60	MAX_ALLOW_SOIL_DISTURBANCE_PCT	NULL	NUMBER(3,1)
	The MAX ALLOW SOIL DISTURBANCE PCT is the maximum percentage of the soil surface which can be disturbed by harvesting or silviculture activities.		
70	VARIANCE_IND	NULL	VARCHAR2(1)
	The VARIANCE IND is a yes/no indicator indicating if the standards unit's stocking standard is under an approved variation. Ex. 'Y' = yes, 'N'=no.		
80	BGC_ZONE_CODE	NULL	VARCHAR2(4)
	The BGC ZONE CODE is the Biogeoclimatic Zone of the SU, according to the Biogeoclimatic Ecosystem Classification (BEC) system. Eg. IDF; MS; CWH.		
90	BGC_SUBZONE_CODE	NULL	VARCHAR2(3)
	The BGC SUBZONE CODE is the Biogeoclimatic sub-zone of the SU, according to the BEC system. Eg. dk; xc; mk.		
100	BGC_VARIANT	NULL	VARCHAR2(1)
	The BGC VARIANT is the Biogeoclimatic subzone-variant, according to the BEC system. Eg. 1, 2.		
110	BGC_PHASE	NULL	VARCHAR2(1)
	The BGC PHASE is the Biogeoclimatic phase, according to the BEC system. Ex. a, w.		
120	BEC_SITE_SERIES	NULL	VARCHAR2(4)
	The BGC SITE SERIES is the site series for the given biogeoclimatic unit, according to the BEC system. Eg. 01, 04, 05.		
130	BEC_SERAL	NULL	VARCHAR2(4)
	The BEC SERIAL is the seral type for certain site series, according to the BEC system. Eg. Accp, Acho.		
140	BEC_SITE_TYPE	NULL	VARCHAR2(3)
	The BEC SITE TYPE is the site type for the given site series, according to the BEC system. Eg. MS, NP.		
150	REGEN_OBLIGATION_IND	NULL	VARCHAR2(1)
	The REGEN OBJECTIVE IND is set to indicate whether the standards unit has free growing stocking standards versus post-harvest stocking requirement required for intermediate cut (eg. commercial thinning) or selection silvicultural system/harvesting disturbance. Ex. 'Y'=yes, 'N'=no.		
160	NO_REGEN_EARLY_OFFSET_YRS	NULL	NUMBER(2,0)
	The NO REGEN EARLY OFFSET YRS represents the minimum year duration before post-harvest inspection is required to confirm residual stocking standards due to intermediate cut or selection silvicultural system.		
170	NO_REGEN_LATE_OFFSET_YRS	NULL	NUMBER(2,0)
	The NO REGEN LATE OFFSET YRS represents the maximum year duration before post-harvest		

Table: RSLT_STANDARDS_UNIT_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	inspection is required to confirm residual stocking standards due to intermediate cut or selection silvicultural system.		
180	NO_REGEN_DUE_EARLY_DATE	NULL	DATE
	The NO REGEN DUE EARLY DATE represents the minimum date before post-harvest inspection is required to confirm residual stocking standards due to intermediate cut or selection silvicultural system.		
190	NO_REGEN_DUE_LATE_DATE	NULL	DATE
	The NO REGEN DUE LATE DATE represents the maximum date before post-harvest inspection is required to confirm residual stocking standards due to intermediate cut or selection silvicultural system.		
200	NO_REGEN_DECLARED_IND	NULL	VARCHAR2(1)
	The NO REGEN DECLARED IND is a system generated flag 'Y/N' which is set when declaration for a standards unit with no Regen Obligation is made.		
210	NO_REGEN_DECLARED_USER	NULL	VARCHAR2(30)
	The NO REGEN DECLARED USER is the name of the individual who declared the no Regen Obligation standards unit post harvesting residual stocking has been met.		
220	NO_REGEN_DECLARED_DATE	NULL	DATE
	The NO REGEN DECLARED DATE is the date of the declaration of the standards unit which has no Regen Obligation indicating that the residual stocking standard has been met. Declarations are optional.		
230	NO_REGEN_DECLARE_SUBMIT_DATE	NULL	DATE
	The NO REGEN DECLARED SUBMIT DATE is the date of the submission of the no regeneration obligation declaration.		
240	POST_HARV_DECLARED_IND	NULL	VARCHAR2(1)
	The POST HARV DECLARED IND is a system generated flag 'Y/N' which is set when a post harvest inspection has been made for the standards unit.		
250	POST_HARV_DECLARED_USER	NULL	VARCHAR2(30)
	The POST HARV DECLARED USER is the name of the individual who provided the post harvest declaration for the standards unit.		
260	POST_HARV_DECLARED_DATE	NULL	DATE
	The POST HARV DECLARED DATE is the date of the post harvest declaration for the standards unit.		
270	POST_HARV_DECLARE_SUBMIT_DATE	NULL	DATE
	The POST HARV DECLARE SUBMIT DATE is the date of the submission of the post harvest declaration date.		
280	REGEN_LATE_OFFSET_YRS	NULL	NUMBER(2,0)
	The REGEN LATE OFFSET YRS is the maximum year for the achievement of the regeneration forest cover survey for the standards unit.		
290	REGEN_DUE_LATE_DATE	NULL	DATE
	The REGEN DUE LATE DATE is the maximum date for the achievement of the regeneration forest cover survey for the standards unit.		
300	REGEN_DECLARED_IND	NULL	VARCHAR2(1)
	The REGEN DECLARED IND is a system generated flag 'Y/N' which is set when a regeneration declaration has been made for the standards unit.		
310	REGEN_DECLARED_USER	NULL	VARCHAR2(30)
	The REGEN DECLARED USER is the name of the individual who provided the regeneration declaration for the standards unit.		
320	REGEN_DECLARED_DATE	NULL	DATE
	The REGEN DECLARED DATE is the date of the regeneration declaration for the standards unit.		
330	REGEN_DECLARE_SUBMIT_DATE	NULL	DATE
	The REGEN DECLARE SUBMIT DATE is the date of the submission of the regeneration declaration date.		
340	FREE_GROW_EARLY_OFFSET_YRS	NULL	NUMBER(2,0)
	The FREE GROW EARLY OFFSET YRS is the minimum year for the reporting of the free growing forest cover survey for the standards unit.		
350	FREE_GROW_LATE_OFFSET_YRS	NULL	NUMBER(2,0)
	The FREE GROW LATE OFFSET YRS is the maximum year for the reporting of the free growing forest cover survey for the standards unit.		
360	FREE_GROW_DUE_EARLY_DATE	NULL	DATE
	The FREE GROW DUE EARLY DATE is the minimum date for the reporting of the free growing forest cover survey for the standards unit.		
370	FREE_GROW_DUE_LATE_DATE	NULL	DATE

Table: RSLT_STANDARDS_UNIT_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	The FREE GROW DUE LATE DATE is the maximum date for the reporting of the free growing forest cover survey for the standards unit.		
380	FREE_GROW_DECLARED_IND	NULL	VARCHAR2(1)
	The FREE GROW DECLARED IND is a system generated flag 'Y/N' which is set when a free growing declaration has been made for the standards unit.		
390	FREE_GROW_DECLARED_USER	NULL	VARCHAR2(30)
	The FREE GROW DECLARED USER is the name of the individual who provided the free growing declaration for the standards unit.		
400	FREE_GROW_DECLARED_DATE	NULL	DATE
	The FREE GROW DECLARE DATE is the date of the free growing declaration for the standards unit.		
410	FREE_GROW_DECLARE_SUBMIT_DATE	NULL	DATE
	The FREE GROW DECLARE SUBMIT DATE is the date of the submission of the free growing declaration date.		
415	STANDARDS_UNIT_TYPE	NULL	VARCHAR2(7)
	The STANDARDS UNIT TYPE describes the standards unit type characteristics: EVEN, UNEVEN, NONE and UNKOWN.		
	The STANDARDS UNIT TYPE describes the standards unit type characteristics: EVEN, UNEVEN, NONE and UNKOWN.		
420	I_MIN_STOCKING_STANDARD	NULL	NUMBER(5,0)
	I MIN STOCKING STANDARD - even-aged stocking standards - Minimum number of trees per hectare of preferred and acceptable species.		
430	I_MIN_PREF_STOCKING_STANDARD	NULL	NUMBER(5,0)
	I MIN PREF STOCKING STANDARD - even-aged stocking standard - Minimum number of trees per hectare of preferred species.		
440	I_TARGET_STOCKING	NULL	NUMBER(5,0)
	I TARGET STOCKING - even-aged stocking standards - Target number of trees per hectare of preferred and acceptable species		
450	I_RESIDUAL_BASAL_AREA	NULL	NUMBER(5,0)
	I RESIDUAL BASAL AREA - even-aged stocking standard. The basal area per hectare left standing after harvest		
460	I_MIN_HORIZONTAL_DISTANCE	NULL	NUMBER(3,1)
	I MIN HORIZONTAL DISTANCE - even-aged stocking standard - minimum horizontal distance between trees in metres.		
470	I_MIN_POST_SPACING	NULL	NUMBER(10,0)
	I MIN POST SPACING - even-aged stocking standard - Minimum density of well-spaced preferred and/or acceptable stems/ha to which the stand must be spaced to achieve free growing status.		
480	I_MAX_POST_SPACING	NULL	NUMBER(10,0)
	I MAX POST SPACING - even-aged stocking standard - Maximum density of well-spaced preferred and/or acceptable stems/ha to which the stand must be spaced to achieve free growing status.		
490	I_MAX_CONIFER	NULL	NUMBER(10,0)
	I MAX CONIFER - even-aged stocking standard - maximum allowable stand density of total countable conifers,m above which openings must be spaced down to a specified density of well-spaced preferred and/or acceptable stems, to achieve free growing status.		
500	I_HEIGHT_RELATIVE_TO_COMP	NULL	NUMBER(5,0)
	I HEIGHT RELATIVE TO COMP - even-aged stocking standard - Required minimum height of the tree above competing vegetation in a 1 metre radius. The unit of measure is expressed as a percentage or cm. Refer to I TREE SIZE UNIT CODE for the unit of measure used.		
510	I_TREE_SIZE_UNIT_CODE	NULL	VARCHAR2(3)
	I TREE SIZE UNIT CODE - even-aged stocking standard - the unit of measure used for I HEIGHT RELATIVE TO COMP (above brush). Either CM-number of centimetres above vegetation, or %-percentage above vegetation.		
520	I_PREFERRED_SPECIES1	NULL	VARCHAR2(8)
	I PREFERRED SPECIES1 - even-aged stocking standard - the preferred species that a healthy, well-spaced tree must attain in order to be considered free growing.		
530	I_PREFERRED_HEIGHT1	NULL	NUMBER(3,1)
	I PREFERRED HEIGHT1- even-aged stocking standard - the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES1 must attain in order to be considered free growing.		

Table: RSLT_STANDARDS_UNIT_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
540	I_PREFERRED_SPECIES2	NULL	VARCHAR2(8)
	I PREFERRED SPECIES2 - even-aged stocking standard - the preferred species that a healthy, well-spaced tree must attain in order to be considered free growing.		
550	I_PREFERRED_HEIGHT2	NULL	NUMBER(3,1)
	I PREFERRED HEIGHT2 - even-aged stocking standard - the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES2 must attain in order to be considered free growing.		
560	I_PREFERRED_SPECIES3	NULL	VARCHAR2(8)
	I PREFERRED SPECIES3 - even-aged stocking standard - the preferred species that a healthy, well-spaced tree must attain in order to be considered free growing.		
570	I_PREFERRED_HEIGHT3	NULL	NUMBER(3,1)
	I PREFERRED HEIGHT3 - even-aged stocking standard - the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES3 must attain in order to be considered free growing.		
580	I_PREFERRED_SPECIES4	NULL	VARCHAR2(8)
	I PREFERRED SPECIES4 - even-aged stocking standard - the preferred species that a healthy, well-spaced tree must attain in order to be considered free growing.		
590	I_PREFERRED_HEIGHT4	NULL	NUMBER(3,1)
	I PREFERRED HEIGHT4 - even-aged stocking standard - the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES4 must attain in order to be considered free growing.		
600	I_PREFERRED_SPECIES5	NULL	VARCHAR2(8)
	I PREFERRED SPECIES5 - even-aged stocking standard - the preferred species that a healthy, well-spaced tree must attain in order to be considered free growing.		
610	I_PREFERRED_HEIGHT5	NULL	NUMBER(3,1)
	I PREFERRED HEIGHT5 - even-aged stocking standard - the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES5 must attain in order to be considered free growing.		
620	I_MORE_PREF_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	I MORE PREF SPECIES EXIST IND - Even-aged stand with more than 5 preferred species than those listed. Y=yes, N=No.		
630	I_ACCEPTABLE_SPECIES1	NULL	VARCHAR2(8)
	I ACCEPTABLE SPECIES1 - even-aged stocking standard - the acceptable species that a healthy, well-spaced tree must attain in order to be considered free growing.		
640	I_ACCEPTABLE_HEIGHT1	NULL	NUMBER(3,1)
	I ACCEPTABLE HEIGHT1 - even-aged stocking standard - the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES1 must attain in order to be considered free growing.		
650	I_ACCEPTABLE_SPECIES2	NULL	VARCHAR2(8)
	I ACCEPTABLE SPECIES2 - even-aged stocking standard - the acceptable species that a healthy, well-spaced tree must attain in order to be considered free growing.		
660	I_ACCEPTABLE_HEIGHT2	NULL	NUMBER(3,1)
	I ACCEPTABLE HEIGHT2 - even-aged stocking standard - the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES2 must attain in order to be considered free growing.		
670	I_ACCEPTABLE_SPECIES3	NULL	VARCHAR2(8)
	I ACCEPTABLE SPECIES3 - even-aged stocking standard - the acceptable species that a healthy, well-spaced tree must attain in order to be considered free growing.		
680	I_ACCEPTABLE_HEIGHT3	NULL	NUMBER(3,1)
	I ACCEPTABLE HEIGHT3 - even-aged stocking standard -the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES3 must attain in order to be considered free growing.		
690	I_ACCEPTABLE_SPECIES4	NULL	VARCHAR2(8)
	I ACCEPTABLE SPECIES4 - even-aged stocking standard - the acceptable species that a healthy, well-spaced tree must attain in order to be considered free growing.		
700	I_ACCEPTABLE_HEIGHT4	NULL	NUMBER(3,1)
	I ACCEPTABLE HEIGHT4 - even-aged stocking standard -the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES4 must attain in order to be considered free growing.		
710	I_ACCEPTABLE_SPECIES5	NULL	VARCHAR2(8)
	I ACCEPTABLE SPECIES5 - even-aged stocking standard -the acceptable species that a healthy, well-		

Table: RSLT_STANDARDS_UNIT_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	spaced tree must attain in order to be considered free growing.		
720	I_ACCEPTABLE_HEIGHT5	NULL	NUMBER(3,1)
	I ACCEPTABLE HEIGHT5 - even-aged stocking standard - the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES5 must attain in order to be considered free growing.		
730	I_MORE_ACC_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	I MORE ACC SPECIES EXIST IND - Even-aged stand with more than 5 acceptable species than those listed.		
740	I1_MIN_STOCKING_STANDARD	NULL	NUMBER(5,0)
	I1 MIN STOCKING STANDARD - uneven-aged stocking standards Layer1- Mature - Minimum number of trees per hectare of preferred and acceptable species.		
750	I1_MIN_PREF_STOCKING_STANDARD	NULL	NUMBER(5,0)
	I1 MIN PREF STOCKING STANDARD - uneven-aged stocking standards Layer1- Mature - Target number of trees per hectare of preferred and acceptable species		
760	I1_TARGET_STOCKING	NULL	NUMBER(5,0)
	I1 TARGET STOCKING - uneven-aged stocking standards Layer 1-Mature - Target number of trees per hectare of preferred and acceptable species		
770	I1_RESIDUAL_BASAL_AREA	NULL	NUMBER(5,0)
	I1 RESIDUAL BASAL AREA - uneven-aged stocking standard Layer 1- Mature. The basal area per hectare left standing after harvest		
780	I1_MIN_HORIZONTAL_DISTANCE	NULL	NUMBER(3,1)
	I1 MIN HORIZONTAL DISTANCE - uneven-aged stocking standard Layer 1- Mature - minimum horizontal distance between trees in metres.		
790	I1_MIN_POST_SPACING	NULL	NUMBER(10,0)
	I1 MIN POST SPACING - uneven-aged stocking standard Layer 1- Mature - Minimum density of well-spaced preferred and/or acceptable stems/ha to which the stand must be spaced to achieve free growing status.		
800	I1_MAX_POST_SPACING	NULL	NUMBER(10,0)
	I1 MAX POST SPACING - uneven-aged stocking standard Layer 1- Mature - Maximum density of well-spaced preferred and/or acceptable stems/ha to which the stand must be spaced to achieve free growing status.		
810	I1_MAX_CONIFER	NULL	NUMBER(10,0)
	I1 MAX CONIFER - uneven-aged stocking standard Layer 1- Mature - maximum allowable stand density of total countable conifers,m above which openings must be spaced down to a specified density of well-spaced preferred and/or acceptable stems, to achieve free growing status.		
820	I1_HEIGHT_RELATIVE_TO_COMP	NULL	NUMBER(5,0)
	I1 HEIGHT RELATIVE TO COMP - uneven-aged stocking standard Layer 1- Mature - Required minimum height of the tree above competing vegetation in a 1 metre radius. The unit of measure is expressed as a percentage or cm. Refer to I1 TREE SIZE UNIT CODE for the unit of measure used.		
830	I1_TREE_SIZE_UNIT_CODE	NULL	VARCHAR2(3)
	I1 TREE SIZE UNIT CODE - even-aged stocking standard Layer 1- Mature - the unit of measure used for I1 HEIGHT RELATIVE TO COMP (above brush). Either CM-number of centimetres above vegetation, or %-percentage above vegetation.		
840	I1_PREFERRED_SPECIES1	NULL	VARCHAR2(8)
	I1 PREFERRED SPECIES1 - uneven-aged Layer 1- Mature stocking standards species1- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
850	I1_PREFERRED_HEIGHT1	NULL	NUMBER(3,1)
	I1 PREFERRED HEIGHT1 - uneven-aged Layer 1- Mature stocking standards species1- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES1 must attain in order to be considered free growing. The tree species comes from the preffered list.		
860	I1_PREFERRED_SPECIES2	NULL	VARCHAR2(8)
	I1 PREFERRED SPECIES2 - uneven-aged Layer 1- Mature stocking standards species2- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
870	I1_PREFERRED_HEIGHT2	NULL	NUMBER(3,1)
	I1 PREFERRED HEIGHT2 - uneven-aged Layer 1- Mature stocking standards species2- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES2 must attain in order to be considered free growing. The tree species comes from the preffered list.		

Table: RSLT_STANDARDS_UNIT_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
880	I1_PREFERRED_SPECIES3	NULL	VARCHAR2(8)
	I1 PREFERRED SPECIES3 - uneven-aged Layer 1- Mature stocking standards species3- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
890	I1_PREFERRED_HEIGHT3	NULL	NUMBER(3,1)
	I1 PREFERRED HEIGHT3 - uneven-aged Layer 1- Mature stocking standards species3- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES3 must attain in order to be considered free growing. The tree species comes from the preffered list.		
900	I1_PREFERRED_SPECIES4	NULL	VARCHAR2(8)
	I1 PREFERRED SPECIES4 - uneven-aged Layer 1- Mature stocking standards species4- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
910	I1_PREFERRED_HEIGHT4	NULL	NUMBER(3,1)
	I1 PREFERRED HEIGHT4 - uneven-aged Layer 1- Mature stocking standards species4- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES4 must attain in order to be considered free growing. The tree species comes from the preffered list.		
920	I1_PREFERRED_SPECIES5	NULL	VARCHAR2(8)
	I1 PREFERRED SPECIES - uneven-aged Layer 1- Mature stocking standards species5- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
930	I1_PREFERRED_HEIGHT5	NULL	NUMBER(3,1)
	I1 PREFERRED HEIGHT5 - uneven-aged Layer 1- Mature stocking standards species5- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES5 must attain in order to be considered free growing. The tree species comes from the preffered list.		
940	I1_MORE_PREF_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	I1 MORE PREF SPECIES EXIST IND - uneven-aged stocking standard Layer 2- Pole. The basal area per hectare left standing after harvest		
950	I1_ACCEPTABLE_SPECIES1	NULL	VARCHAR2(8)
	I1 ACCEPTABLE SPECIES1 - uneven-aged Layer 1- Mature stocking standards species1- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
960	I1_ACCEPTABLE_HEIGHT1	NULL	NUMBER(3,1)
	I1 ACCEPTABLE HEIGHT1 - uneven-aged Layer 1- Mature stocking standards species1- the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES1 must attain in order to be considered free growing.		
970	I1_ACCEPTABLE_SPECIES2	NULL	VARCHAR2(8)
	I1 ACCEPTABLE SPECIES2 - uneven-aged Layer 1- Mature stocking standards species2- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
980	I1_ACCEPTABLE_HEIGHT2	NULL	NUMBER(3,1)
	I1 ACCEPTABLE HEIGHT2 - uneven-aged Layer 1- Mature stocking standards species2- the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES2 must attain in order to be considered free growing.		
990	I1_ACCEPTABLE_SPECIES3	NULL	VARCHAR2(8)
	I1 ACCEPTABLE SPECIES3 - uneven-aged Layer 1- Mature stocking standards species3- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1000	I1_ACCEPTABLE_HEIGHT3	NULL	NUMBER(3,1)
	I1 ACCEPTABLE HEIGHT3 - uneven-aged Layer 1- Mature stocking standards species3- the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES3 must attain in order to be considered free growing.		
1010	I1_ACCEPTABLE_SPECIES4	NULL	VARCHAR2(8)
	I1 ACCEPTABLE SPECIES4 - uneven-aged Layer 1- Mature stocking standards species4- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1020	I1_ACCEPTABLE_HEIGHT4	NULL	NUMBER(3,1)
	I1 ACCEPTABLE HEIGHT4 - uneven-aged Layer 1- Mature stocking standards species4- the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES4 must attain in order to be considered free growing.		
1030	I1_ACCEPTABLE_SPECIES5	NULL	VARCHAR2(8)
	I1 ACCEPTABLE SPECIES5 - uneven-aged Layer 1- Mature stocking standards species5- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1040	I1_ACCEPTABLE_HEIGHT5	NULL	NUMBER(3,1)
	I1 ACCEPTABLE HEIGHT5 - uneven-aged Layer 1- Mature stocking standards species5- the minimum		

Table: RSLT_STANDARDS_UNIT_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES5 must attain in order to be considered free growing.		
1050	I1_MORE_ACC_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	I1 MORE ACC SPECIES EXIST IND- uneven-aged Layer 1-Mature with more than 5 acceptable species than those listed.		
1060	I2_MIN_STOCKING_STANDARD	NULL	NUMBER(5,0)
	I2 MIN STOCKING STANDARD - uneven-aged stocking standards Layer2- Pole - Minimum number of trees per hectare of preferred and acceptable species.		
1070	I2_MIN_PREF_STOCKING_STANDARD	NULL	NUMBER(5,0)
	I2 MIN PREF STOCKING STANDARD - uneven-aged stocking standards Layer2- Pole - Target number of trees per hectare of preferred and acceptable species		
1080	I2_TARGET_STOCKING	NULL	NUMBER(5,0)
	I2 TARGET STOCKING - uneven-aged stocking standards Layer 2-Pole - Target number of trees per hectare of preferred and acceptable species		
1090	I2_RESIDUAL_BASAL_AREA	NULL	NUMBER(5,0)
	I2 RESIDUAL BASAL AREA - uneven-aged stocking standard Layer 2- Pole. The basal area per hectare left standing after harvest		
1100	I2_MIN_HORIZONTAL_DISTANCE	NULL	NUMBER(3,1)
	I2 MIN HORIZONTAL DISTANCE - uneven-aged stocking standard Layer 2- Pole - minimum horizontal distance between trees in metres.		
1110	I2_MIN_POST_SPACING	NULL	NUMBER(10,0)
	I2 MIN POST SPACING - uneven-aged stocking standard Layer 2- Pole - Minimum density of well-spaced preferred and/or acceptable stems/ha to which the stand must be spaced to achieve free growing status.		
1120	I2_MAX_POST_SPACING	NULL	NUMBER(10,0)
	I2 MAX POST SPACING - uneven-aged stocking standard Layer 2- Pole - Maximum density of well-spaced preferred and/or acceptable stems/ha to which the stand must be spaced to achieve free growing status.		
1130	I2_MAX_CONIFER	NULL	NUMBER(10,0)
	I2 MAX CONIFER - uneven-aged stocking standard Layer 2- Pole - maximum allowable stand density of total countable conifers,m above which openings must be spaced down to a specified density of well-spaced preferred and/or acceptable stems, to achieve free growing status.		
1140	I2_HEIGHT_RELATIVE_TO_COMP	NULL	NUMBER(5,0)
	I2 HEIGHT RELATIVE TO COMP - uneven-aged stocking standard Layer 2- Pole - Required minimum height of the tree above competing vegetation in a 1 metre radius. The unit of measure is expressed as a percentage or cm. Refer to I2 TREE SIZE UNIT CODE for the unit of measure used.		
1150	I2_TREE_SIZE_UNIT_CODE	NULL	VARCHAR2(3)
	I2 TREE SIZE UNIT CODE - uneven-aged stocking standard Layer 2- Pole - the unit of measure used for I2 HEIGHT RELATIVE TO COMP (above brush). Either CM-number of centimetres above vegetation, or %-percentage above vegetation.		
1160	I2_PREFERRED_SPECIES1	NULL	VARCHAR2(8)
	I2 PREFERRED SPECIES1 - uneven-aged Layer 2- Pole stocking standards species1- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1170	I2_PREFERRED_HEIGHT1	NULL	NUMBER(3,1)
	I2 PREFERRED HEIGHT1 - uneven-aged Layer 2- Pole stocking standards species1- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES1 must attain in order to be considered free growing. The tree species comes from the preffered list.		
1180	I2_PREFERRED_SPECIES2	NULL	VARCHAR2(8)
	I2 PREFERRED SPECIES2 - uneven-aged Layer 2- Pole stocking standards species2- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1190	I2_PREFERRED_HEIGHT2	NULL	NUMBER(3,1)
	I2 PREFERRED HEIGHT2 - uneven-aged Layer 2- Pole stocking standards species2- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES2 must attain in order to be considered free growing. The tree species comes from the preffered list.		
1200	I2_PREFERRED_SPECIES3	NULL	VARCHAR2(8)
	I2 PREFERRED SPECIES3 - uneven-aged Layer 2- Pole stocking standards species3- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1210	I2_PREFERRED_HEIGHT3	NULL	NUMBER(3,1)

Table: RSLT_STANDARDS_UNIT_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	I2 PREFERRED HEIGHT3 - uneven-aged Layer 2- Pole stocking standards species3- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES3 must attain in order to be considered free growing. The tree species comes from the preffered list.		
1220	I2_PREFERRED_SPECIES4	NULL	VARCHAR2(8)
	I2 PREFERRED SPECIES4 - uneven-aged Layer 2- Pole stocking standards species4- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1230	I2_PREFERRED_HEIGHT4	NULL	NUMBER(3,1)
	I2 PREFERRED HEIGHT4 - uneven-aged Layer 2- Pole stocking standards species4- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES4 must attain in order to be considered free growing. The tree species comes from the preffered list.		
1240	I2_PREFERRED_SPECIES5	NULL	VARCHAR2(8)
	I2 PREFERRED SPECIES5 - uneven-aged Layer 2- Pole stocking standards species5- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1250	I2_PREFERRED_HEIGHT5	NULL	NUMBER(3,1)
	I2 PREFERRED HEIGHT5 - uneven-aged Layer 2- Pole stocking standards species5- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES5 must attain in order to be considered free growing. The tree species comes from the preffered list.		
1260	I2_MORE_PREF_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	I2 MORE PREF SPECIES EXIST IND - Uneven-aged stand - Layer 2-Pole with more than 5 preferred species than those listed.		
1270	I2_ACCEPTABLE_SPECIES1	NULL	VARCHAR2(8)
	I2 ACCEPTABLE HEIGHT1 - uneven-aged Layer 2- Pole stocking standards species1- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1280	I2_ACCEPTABLE_HEIGHT1	NULL	NUMBER(3,1)
	I2 ACCEPTABLE HEIGHT1 - uneven-aged Layer 2- Pole stocking standards species1- the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES1 must attain in order to be considered free growing.		
1290	I2_ACCEPTABLE_SPECIES2	NULL	VARCHAR2(8)
	I2 ACCEPTABLE SPECIES2 - uneven-aged Layer 2- Pole stocking standards species2- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1300	I2_ACCEPTABLE_HEIGHT2	NULL	NUMBER(3,1)
	I2 ACCEPTABLE HEIGHT2 - uneven-aged Layer 2- Pole stocking standards species2- the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES2 must attain in order to be considered free growing.		
1310	I2_ACCEPTABLE_SPECIES3	NULL	VARCHAR2(8)
	I2 ACCEPTABLE SPECIES3 - uneven-aged Layer 2- Pole stocking standards species3- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1320	I2_ACCEPTABLE_HEIGHT3	NULL	NUMBER(3,1)
	I2 ACCEPTABLE HEIGHT3 - uneven-aged Layer 2- Pole stocking standards species3- the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES3 must attain in order to be considered free growing.		
1330	I2_ACCEPTABLE_SPECIES4	NULL	VARCHAR2(8)
	I2 ACCEPTABLE SPECIES4 - uneven-aged Layer 2- Pole stocking standards species4- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1340	I2_ACCEPTABLE_HEIGHT4	NULL	NUMBER(3,1)
	I2 ACCEPTABLE HEIGHT4 - uneven-aged Layer 2- Pole stocking standards species4- the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES4 must attain in order to be considered free growing.		
1350	I2_ACCEPTABLE_SPECIES5	NULL	VARCHAR2(8)
	I2 ACCEPTABLE SPECIES5 - uneven-aged Layer 2- Pole stocking standards species5- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1360	I2_ACCEPTABLE_HEIGHT5	NULL	NUMBER(3,1)
	I2 ACCEPTABLE HEIGHT5 - uneven-aged Layer 2- Pole stocking standards species5- the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES5 must attain in order to be considered free growing.		
1370	I2_MORE_ACC_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	I2 MORE ACC SPECIES EXIST IND - Uneven-aged stand - Layer 2-Pole with more than 5 acceptable		

Table: RSLT_STANDARDS_UNIT_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	species than those listed.		
1380	I3_MIN_STOCKING_STANDARD	NULL	NUMBER(5,0)
	I3 MIN STOCKING STANDARD - uneven-aged stocking standards Layer3- Sapling - Minimum number of trees per hectare of preferred and acceptable species.		
1390	I3_MIN_PREF_STOCKING_STANDARD	NULL	NUMBER(5,0)
	I3 MIN PREF STOCKING STANDARD - uneven-aged stocking standards Layer3- Sapling - Target number of trees per hectare of preferred and acceptable species		
1400	I3_TARGET_STOCKING	NULL	NUMBER(5,0)
	I3 TARGET STOCKING - uneven-aged stocking standards Layer 3-Sapling - Target number of trees per hectare of preferred and acceptable species		
1410	I3_RESIDUAL_BASAL_AREA	NULL	NUMBER(5,0)
	Residual Basal Area - uneven-aged stocking standard Layer 3- Sapling. The basal area per hectare left standing after harvest		
1420	I3_MIN_HORIZONTAL_DISTANCE	NULL	NUMBER(3,1)
	I3 MIN HORIZONTAL DISTANCE - uneven-aged stocking standard Layer 3- Sapling - minimum horizontal distance between trees in metres.		
1430	I3_MIN_POST_SPACING	NULL	NUMBER(10,0)
	I3 MIN POST SPACING - uneven-aged stocking standard Layer 3- Sapling - Minimum density of well-spaced preferred and/or acceptable stems/ha to which the stand must be spaced to achieve free growing status.		
1440	I3_MAX_POST_SPACING	NULL	NUMBER(10,0)
	I3 MAX POST SPACING - uneven-aged stocking standard Layer 3- Sapling - Maximum density of well-spaced preferred and/or acceptable stems/ha to which the stand must be spaced to achieve free growing status.		
1450	I3_MAX_CONIFER	NULL	NUMBER(10,0)
	I3 MAX CONIFER - uneven-aged stocking standard Layer 3- Sapling - maximum allowable stand density of total countable conifers,m above which openings must be spaced down to a specified density of well-spaced preferred and/or acceptable stems, to achieve free growing status.		
1460	I3_HEIGHT_RELATIVE_TO_COMP	NULL	NUMBER(5,0)
	I3 HEIGHT RELATIVE TO COMP - uneven-aged stocking standard Layer 3- Sapling - Required minimum height of the tree above competing vegetation in a 1 metre radius. The unit of measure is expressed as a percentage or cm. Refer to I3 TREE SIZE UNIT CODE for the unit of measure used.		
1470	I3_TREE_SIZE_UNIT_CODE	NULL	VARCHAR2(3)
	I3 TREE SIZE UNIT CODE - uneven-aged stocking standard Layer 3- Sapling - the unit of measure used for I3 HEIGHT RELATIVE TO COMP (above brush). Either CM-number of centimetres above vegetation, or %-percentage above vegetation.		
1480	I3_PREFERRED_SPECIES1	NULL	VARCHAR2(8)
	I3 PREFERRED SPECIES1- uneven-aged Layer 3- Sapling stocking standards species1- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1490	I3_PREFERRED_HEIGHT1	NULL	NUMBER(3,1)
	I3 PREFERRED HEIGHT1 - uneven-aged Layer 3- Sapling stocking standards species1- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES1 must attain in order to be considered free growing. The tree species comes from the preffered list.		
1500	I3_PREFERRED_SPECIES2	NULL	VARCHAR2(8)
	I3 PREFERRED SPECIES2 - uneven-aged Layer 3- Sapling stocking standards species2- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1510	I3_PREFERRED_HEIGHT2	NULL	NUMBER(3,1)
	I3 PREFERRED HEIGHT2 - uneven-aged Layer 3- Sapling stocking standards species2- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES2 must attain in order to be considered free growing. The tree species comes from the preffered list.		
1520	I3_PREFERRED_SPECIES3	NULL	VARCHAR2(8)
	I3 PREFERRED SPECIES3 - uneven-aged Layer 3- Sapling stocking standards species3- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1530	I3_PREFERRED_HEIGHT3	NULL	NUMBER(3,1)
	I3 PREFERRED HEIGHT3 - uneven-aged Layer 3- Sapling stocking standards species3- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES3 must attain in order to be considered free growing. The tree species comes from the preffered list.		

Table: RSLT_STANDARDS_UNIT_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
1540	I3_PREFERRED_SPECIES4	NULL	VARCHAR2(8)
	I3 PREFERRED SPECIES4 - uneven-aged Layer 3- Sapling stocking standards species4- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1550	I3_PREFERRED_HEIGHT4	NULL	NUMBER(3,1)
	I3 PREFERRED HEIGHT4 - uneven-aged Layer 3- Sapling stocking standards species4- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES4 must attain in order to be considered free growing. The tree species comes from the preffered list.		
1560	I3_PREFERRED_SPECIES5	NULL	VARCHAR2(8)
	I3 PREFERRED SPECIES5 - uneven-aged Layer 3- Sapling stocking standards species5- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1570	I3_PREFERRED_HEIGHT5	NULL	NUMBER(3,1)
	I3 PREFERRED HEIGHT5 - uneven-aged Layer 3- Sapling stocking standards species5- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES5 must attain in order to be considered free growing. The tree species comes from the preffered list.		
1580	I3_MORE_PREF_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	I3 MORE PREF SPECIES EXIST IND - Uneven-aged stand - Layer 3-Sapling with more than 5 preferred species than those listed.		
1590	I3_ACCEPTABLE_SPECIES1	NULL	VARCHAR2(8)
	I3 ACCEPTABLE SPECIES1 - uneven-aged Layer 3- Sapling stocking standards species1- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1600	I3_ACCEPTABLE_HEIGHT1	NULL	NUMBER(3,1)
	I3 ACCEPTABLE HEIGHT1 - uneven-aged Layer 3- Sapling stocking standards species1- the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES1 must attain in order to be considered free growing.		
1610	I3_ACCEPTABLE_SPECIES2	NULL	VARCHAR2(8)
	I3 ACCEPTABLE SPECIES2 - uneven-aged Layer 3- Sapling stocking standards species2- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1620	I3_ACCEPTABLE_HEIGHT2	NULL	NUMBER(3,1)
	I3 ACCEPTABLE HEIGHT2 - uneven-aged Layer 3- Sapling stocking standards species2- the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES2 must attain in order to be considered free growing.		
1630	I3_ACCEPTABLE_SPECIES3	NULL	VARCHAR2(8)
	I3 ACCEPTABLE SPECIE3 - uneven-aged Layer 3- Sapling stocking standards species3- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1640	I3_ACCEPTABLE_HEIGHT3	NULL	NUMBER(3,1)
	I3 ACCEPTABLE HEIGHT3 - uneven-aged Layer 3- Sapling stocking standards species3- the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES3 must attain in order to be considered free growing.		
1650	I3_ACCEPTABLE_SPECIES4	NULL	VARCHAR2(8)
	I3 ACCEPTABLE SPECIES4 - uneven-aged Layer 3- Sapling stocking standards species4- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1660	I3_ACCEPTABLE_HEIGHT4	NULL	NUMBER(3,1)
	I3 ACCEPTABLE HEIGHT4 - uneven-aged Layer 3- Sapling stocking standards species4- the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES4 must attain in order to be considered free growing.		
1670	I3_ACCEPTABLE_SPECIES5	NULL	VARCHAR2(8)
	I3 ACCEPTABLE SPECIES5 - uneven-aged Layer 3- Sapling stocking standards species5- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1680	I3_ACCEPTABLE_HEIGHT5	NULL	NUMBER(3,1)
	I3 ACCEPTABLE HEIGHT5 - uneven-aged Layer 3- Sapling stocking standards species5- the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES5 must attain in order to be considered free growing.		
1690	I3_MORE_ACC_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	I3 MORE ACC SPECIES EXIST IND - Uneven-aged stand - Layer 3- Sapling with more than 5 acceptable species than those listed.		
1700	I4_MIN_STOCKING_STANDARD	NULL	NUMBER(5,0)
	I4 MIN STOCKING STANDARD - uneven-aged stocking standards Layer 4- Regen - Minimum number of		

Table: RSLT_STANDARDS_UNIT_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	trees per hectare of preferred and acceptable species.		
1710	I4_MIN_PREF_STOCKING_STANDARD I4 MIN PREF STOCKING STANDARD - uneven-aged stocking standards Layer 4- Regen - Target number of trees per hectare of preferred and acceptable species	NULL	NUMBER(5,0)
1720	I4_TARGET_STOCKING I4 TARGET STOCKING - uneven-aged stocking standards Layer 4-Regen - Target number of trees per hectare of preferred and acceptable species	NULL	NUMBER(5,0)
1730	I4_RESIDUAL_BASAL_AREA I4 RESIDUAL BASAL AREA - uneven-aged stocking standard Layer 4- Regen. The basal area per hectare left standing after harvest	NULL	NUMBER(5,0)
1740	I4_MIN_HORIZONTAL_DISTANCE I4 MIN HORIZONTAL DISTANCE - uneven-aged stocking standard Layer 4- Regen - minimum horizontal distance between trees in metres.	NULL	NUMBER(3,1)
1750	I4_MIN_POST_SPACING I4 MIN POST SPACING - uneven-aged stocking standard Layer 4- Regen - Minimum density of well-spaced preferred and/or acceptable stems/ha to which the stand must be spaced to achieve free growing status.	NULL	NUMBER(10,0)
1760	I4_MAX_POST_SPACING I4 MAX POST SPACING - uneven-aged stocking standard Layer 4- Regen - Maximum density of well-spaced preferred and/or acceptable stems/ha to which the stand must be spaced to achieve free growing status.	NULL	NUMBER(10,0)
1770	I4_MAX_CONIFER I4 MAX CONIFER- uneven-aged stocking standard Layer 4- Regen - maximum allowable stand density of total countable conifers,m above which openings must be spaced down to a specified density of well-spaced preferred and/or acceptable stems, to achieve free growing status.	NULL	NUMBER(10,0)
1780	I4_HEIGHT_RELATIVE_TO_COMP I4 HEIGHT RELATIVE TO COMP - uneven-aged stocking standard Layer 4- Regen - Required minimum height of the tree above competing vegetation in a 1 metre radius. The unit of measure is expressed as a percentage or cm. Refer to I4 TREE SIZE UNIT CODE for the unit of measure used.	NULL	NUMBER(5,0)
1790	I4_TREE_SIZE_UNIT_CODE I4 TREE SIZE UNIT CODE - uneven-aged stocking standard Layer 4- Regen - the unit of measure used for I4 HEIGHT RELATIVE TO COMP (above brush). Either CM-number of centimetres above vegetation, or %-percentage above vegetation.	NULL	VARCHAR2(3)
1800	I4_PREFERRED_SPECIES1 I4 PREFERRED SPECIES1 - uneven-aged Layer4- Regen stocking standards species1- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.	NULL	VARCHAR2(8)
1810	I4_PREFERRED_HEIGHT1 I4 PREFERRED HEIGHT1- uneven-aged Layer4- Regen stocking standards species1- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES1 must attain in order to be considered free growing. The tree species comes from the preffered list.	NULL	NUMBER(3,1)
1820	I4_PREFERRED_SPECIES2 I4 PREFERRED SPECIES2 - uneven-aged Layer4- Regen stocking standards species2- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.	NULL	VARCHAR2(8)
1830	I4_PREFERRED_HEIGHT2 I4 PREFERRED HEIGHT2 - uneven-aged Layer4- Regen stocking standards species2- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES2 must attain in order to be considered free growing. The tree species comes from the preffered list.	NULL	NUMBER(3,1)
1840	I4_PREFERRED_SPECIES3 I4 PREFERRED SPECIES3 - uneven-aged Layer4- Regen stocking standards species3- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.	NULL	VARCHAR2(8)
1850	I4_PREFERRED_HEIGHT3 I4 PREFERRED HEIGHT3 - uneven-aged Layer4- Regen stocking standards species3- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES3 must attain in order to be considered free growing. The tree species comes from the preffered list.	NULL	NUMBER(3,1)
1860	I4_PREFERRED_SPECIES4 I4 PREFERRED SPECIES4 - uneven-aged Layer4- Regen stocking standards species4- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.	NULL	VARCHAR2(8)

Table: RSLT_STANDARDS_UNIT_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
1870	I4_PREFERRED_HEIGHT4	NULL	NUMBER(3,1)
	I4 PREFERRED HEIGHT4 - uneven-aged Layer4- Regen stocking standards species4- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES4 must attain in order to be considered free growing. The tree species comes from the preffered list.		
1880	I4_PREFERRED_SPECIES5	NULL	VARCHAR2(8)
	I4 PREFERRED SPECIES5 - uneven-aged Layer4- Regen stocking standards species5- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1890	I4_PREFERRED_HEIGHT5	NULL	NUMBER(3,1)
	I4 PREFERRED HEIGHT5 - uneven-aged Layer4- Regen stocking standards species5- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES5 must attain in order to be considered free growing. The tree species comes from the preffered list.		
1900	I4_MORE_PREF_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	I4 MORE PREF SPECIES EXIST IND - Uneven-aged stand - Layer 4-Regen with more than 5 preferred species than those listed.		
1910	I4_ACCEPTABLE_SPECIES1	NULL	VARCHAR2(8)
	I4 ACCEPTABLE SPECIES1 - uneven-aged Layer4- Regen stocking standards species1- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1920	I4_ACCEPTABLE_HEIGHT1	NULL	NUMBER(3,1)
	I4 ACCEPTABLE HEIGHT1 - uneven-aged Layer4- Regen stocking standards species1- the minimum height, in meters, that a healthy, well-spaced tree of species I PREFERRED SPECIES1 must attain in order to be considered free growing. The tree species comes from the acceptable list.		
1930	I4_ACCEPTABLE_SPECIES2	NULL	VARCHAR2(8)
	I4 ACCEPTABLE SPECIES2 - uneven-aged Layer4- Regen stocking standards species2- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1940	I4_ACCEPTABLE_HEIGHT2	NULL	NUMBER(3,1)
	I4 ACCEPTABLE HEIGHT2 - uneven-aged Layer4- Regen stocking standards species2- the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES2 must attain in order to be considered free growing. The tree species comes from the acceptable list.		
1950	I4_ACCEPTABLE_SPECIES3	NULL	VARCHAR2(8)
	I4 ACCEPTABLE SPECIES3 - uneven-aged Layer4- Regen stocking standards species3- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1960	I4_ACCEPTABLE_HEIGHT3	NULL	NUMBER(3,1)
	I4 ACCEPTABLE HEIGHT3 - uneven-aged Layer4- Regen stocking standards species3- the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES3 must attain in order to be considered free growing. The tree species comes from the acceptable list.		
1970	I4_ACCEPTABLE_SPECIES4	NULL	VARCHAR2(8)
	I4 ACCEPTABLE SPECIES4 - uneven-aged Layer4- Regen stocking standards species4- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1980	I4_ACCEPTABLE_HEIGHT4	NULL	NUMBER(3,1)
	I4 ACCEPTABLE HEIGHT4 - uneven-aged Layer4- Regen stocking standards species4- the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES4 must attain in order to be considered free growing. The tree species comes from the acceptable list.		
1990	I4_ACCEPTABLE_SPECIES5	NULL	VARCHAR2(8)
	I4 ACCEPTABLE SPECIES5 - uneven-aged Layer4- Regen stocking standards species5- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
2000	I4_ACCEPTABLE_HEIGHT5	NULL	NUMBER(3,1)
	I4 ACCEPTABLE HEIGHT5 - uneven-aged Layer4- Regen stocking standards species5- the minimum height, in meters, that a healthy, well-spaced tree of species I ACCEPTABLE SPECIES5 must attain in order to be considered free growing. The tree species comes from the acceptable list.		
2010	I4_MORE_ACC_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	I4 MORE ACC SPECIES EXIST IND - Uneven-aged stand - Layer 4-Regen with more than 5 acceptable species than those listed.		
2020	GEOMETRY_EXIST_IND	NULL	VARCHAR2(1)
	The GEOMETRY EXIST IND indicates if there is geometry for the opening. A value of 'Y' indicates there is geometry. A value of 'N' indicates there is no geometry.		
2030	FEATURE_AREA	NULL	NUMBER(11,4)
	The FEATURE AREA is the area of the standards unit in hectares.		

Table: RSLT_STANDARDS_UNIT_POLY (cont'd)

Columns:

Seq.	Column	Nulls?	Type
2040	FEATURE_PERIMETER	NULL	NUMBER(11,4)
	The FEATURE PERIMETER is the perimeter of the standards unit in kilometers.		
2050	CAPTURE_METHOD_CODE	NULL	VARCHAR2(30)
	The CAPTURE METHOD CODE is a code defining the capture method. (e.g. digitize).		
2060	DATA_SOURCE_CODE	NULL	VARCHAR2(10)
	The DATA SOURCE CODE is a code defining the source of the spatial feature (e.g. GPS, TRIM).		
2070	OBSERVATION_DATE	NULL	DATE
	The OBSERVATION DATE is the geometry collection date.		
2080	DATA_QUALITY_COMMENT	NULL	VARCHAR(255)
	The DATA QUALITY COMMENT is a comment indicating the Geometry accuracy.		
2090	SSU_WHO_CREATED	NOT NULL	VARCHAR2(30)
	The SSU WHO CREATED is the USERID of the individual who created the standards unit record.		
2100	SSU_WHEN_CREATED	NOT NULL	DATE
	The SSU WHEN CREATED is the date and time when the standards unit record was created.		
2110	SSU_WHO_UPDATED	NOT NULL	VARCHAR2(30)
	The SSU WHO UPDATED is the USERID of the individual who last updated the standards unit record.		
2120	SSU_WHEN_UPDATED	NOT NULL	DATE
	The SSU WHEN UPDATED is the date and time when the standards unit record was last updated.		
2130	CHANGE_TIMESTAMP1	NULL	DATE
	The date and time of the last update to the STOCKING STANDARD UNIT table.		
2140	CHANGE_TIMESTAMP2	NULL	DATE
	The date and time of the last update to the STOCKING STANDARD GEOMETRY table.		
2150	CHANGE_TIMESTAMP3	NULL	DATE
	The date and time of the last update to the STOCKING LAYER table.		
2160	CHANGE_TIMESTAMP4	NULL	DATE
	The date and time of the last update to the STOCKING LAYER SPECIES table.		
2170	CHANGE_COUNT1	NULL	NUMBER(2)
	A count of all of the STOCKING LAYER species records that related to this record.		
2180	CHANGE_COUNT2	NULL	NUMBER(2)
	A count of all of the STOCKING LAYER records that relate to this record.		
2190	FEATURE_CLASS_SKEY	NULL	NUMBER(10,0)
	The FEATURE CLASS SKEY is the unique key assigned to a Feature Class by the Ministry of Forests.		
2200	GEOMETRY	NULL	
	The GEOMETRY is the standards unit geographical representation.		
2210	OBJECTID	NOT NULL	INTEGER
	The OBJECTID is a system generated value uniquely identifying the opening. Used by SDE.		

Unique Constraints:

RSLT_SU_UK
- OBJECTID

Foreign Keys:

RSLT_SU_RSLT_OPEN_FK
- OPENING_ID = RSLT_OPENING_POLYGON.OPENING_ID

Indexes:

RSLT_SU_GEOM_I
- GEOMETRY

RSLT_SU_RSLT_OPEN_FK_I
- OPENING_ID

RSLT_SU_SU_I
- STANDARDS_UNIT_ID

Table: RSLT_STANDARDS_UNIT_SVW

Description:

The spatial representation for a stocking standard, which is a basic Silviculture objective stated in quantifiable terms for a specific area. These are the acceptable standards for reforestation and soil conversation. Also known as SU - Standards Unit.

Columns:

Seq.	Column	Nulls?	Type
10	STOCKING_STANDARD_UNIT_ID	NOT NULL	NUMBER(10,0)
	The STOCKING STANDARD UNIT ID is a system-generated value by RESULTS to uniquely identify standards units.		
20	STANDARDS_UNIT_ID	NULL	VARCHAR2(4)
	The STANDARDS UNIT ID is an assigned unique identifier that represents the standards units which is apart of a opening for which one or parts were there is similar soil disturbance, regeneration and free growing dates, stocking standards and free growing height that contributes to the establishing free growing stand on the opening.		
30	STANDARDS_REGIME_ID	NULL	NUMBER(10,0)
	The STANDARDS REGIME ID is that assigned unique identifier representing an approved stocking standard applied to the Standards Unit.		
40	OPENING_ID	NOT NULL	NUMBER(10,0)
	The OPENING ID is a system generated value by RESULTS to uniquely identify the opening.		
45	MAP_LABEL	NOT NULL	VARCHAR2(4)
	The default label to be used when displaying the feature on a map. Consists of the STANDARDS UNIT ID.		
50	NET_AREA	NULL	NUMBER(7,1)
	This NET AREA is the net area of the Standards Unit (ie. does not include roads, reserves, non-productive areas).		
60	MAX_ALLOW_SOIL_DISTURBANCE_PCT	NULL	NUMBER(3,1)
	The MAX ALLOW SOIL DISTURBANCE PCT is the maximum percentage of the soil surface which can be disturbed by harvesting or silviculture activities.		
70	VARIANCE_IND	NULL	VARCHAR2(1)
	The VARIANCE IND is a yes/no indicator indicating if the standards unit's stocking standard is under an approved variation.		
80	BGC_ZONE_CODE	NULL	VARCHAR2(4)
	The BGC ZONE CODE is the Biogeoclimatic Zone of the SU, according to the Biogeoclimatic Ecosystem Classification (BEC) system. Eg. IDF; MS; CWH.		
90	BGC_SUBZONE_CODE	NULL	VARCHAR2(3)
	The BGC SUBZONE CODE is the Biogeoclimatic sub-zone of the SU, according to the BEC system. Eg. dk; xc; mk.		
100	BGC_VARIANT	NULL	VARCHAR2(1)
	The BGC VARIANT is the Biogeoclimatic subzone-variant, according to the BEC system. Eg. 1, 2.		
110	BGC_PHASE	NULL	VARCHAR2(1)
	The BGC PHASE is the Biogeoclimatic phase, according to the BEC system.		
120	BEC_SITE_SERIES	NULL	VARCHAR2(4)
	The BGC SITE SERIES is the site series for the given biogeoclimatic unit, according to the BEC system. Eg. 01, 04, 05.		
130	BEC_SERAL	NULL	VARCHAR2(4)
	The BEC SERIAL is the seral type for certain site series, according to the BEC system.		
140	BEC_SITE_TYPE	NULL	VARCHAR2(3)
	The BEC SITE TYPE is the site type for the given site series, according to the BEC system.		
150	REGEN_OBLIGATION_IND	NULL	VARCHAR2(1)
	The REGEN OBJECTIVE IND is set to indicate whether the standards unit has free growing stocking standards versus post-harvest stocking requirement required for intermediate cut (eg. commercial thinning) or selection silvicultural system/harvesting disturbance.		
160	NO_REGEN_EARLY_OFFSET_YRS	NULL	NUMBER(2,0)
	The NO REGEN EARLY OFFSET YRS represents the minimum year duration before post-harvest inspection is required to confirm residual stocking standards due to intermediate cut or selection silvicultural system.		
170	NO_REGEN_LATE_OFFSET_YRS	NULL	NUMBER(2,0)
	The NO REGEN LATE OFFSET YRS represents the maximum year duration before post-harvest		

Table: RSLT_STANDARDS_UNIT_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	inspection is required to confirm residual stocking standards due to intermediate cut or selection silvicultural system.		
180	NO_REGEN_DUE_EARLY_DATE	NULL	DATE
	The NO REGEN DUE EARLY DATE represents the minimum date before post-harvest inspection is required to confirm residual stocking standards due to intermediate cut or selection silvicultural system.		
190	NO_REGEN_DUE_LATE_DATE	NULL	DATE
	The NO REGEN DUE LATE DATE represents the maximum date before post-harvest inspection is required to confirm residual stocking standards due to intermediate cut or selection silvicultural system.		
200	NO_REGEN_DECLARED_IND	NULL	VARCHAR2(1)
	The NO REGEN DECLARED IND is a system generated flag 'Y/N' which is set when declaration for a standards unit with no Regen Obligation is made.		
210	NO_REGEN_DECLARED_USER	NULL	VARCHAR2(30)
	The NO REGEN DECLARED USER is the name of the individual who declared the no Regen Obligation standards unit post harvesting residual stocking has been met.		
220	NO_REGEN_DECLARED_DATE	NULL	DATE
	The NO REGEN DECLARED DATE is the date of the declaration of the standards unit which has no Regen Obligation indicating that the residual stocking standard has been met. Declarations are optional.		
230	NO_REGEN_DECLARE_SUBMIT_DATE	NULL	DATE
	The NO REGEN DECLARED SUBMIT DATE is the date of the submission of the no regeneration obligation declaration.		
240	POST_HARV_DECLARED_IND	NULL	VARCHAR2(1)
	The POST HARV DECLARED IND is a system generated flag 'Y/N' which is set when a post harvest inspection has been made for the standards unit.		
250	POST_HARV_DECLARED_USER	NULL	VARCHAR2(30)
	The POST HARV DECLARED USER is the name of the individual who provided the post harvest declaration for the standards unit.		
260	POST_HARV_DECLARED_DATE	NULL	DATE
	The POST HARV DECLARED DATE is the date of the post harvest declaration for the standards unit.		
270	POST_HARV_DECLARE_SUBMIT_DATE	NULL	DATE
	The POST HARV DECLARE SUBMIT DATE is the date of the submission of the post harvest declaration date.		
280	REGEN_LATE_OFFSET_YRS	NULL	NUMBER(2,0)
	The REGEN LATE OFFSET YRS is the maximum year for the achievement of the regeneration forest cover survey for the standards unit.		
290	REGEN_DUE_LATE_DATE	NULL	DATE
	The REGEN DUE LATE DATE is the maximum date for the achievement of the regeneration forest cover survey for the standards unit.		
300	REGEN_DECLARED_IND	NULL	VARCHAR2(1)
	The REGEN DECLARED IND is a system generated flag 'Y/N' which is set when a regeneration declaration has been made for the standards unit.		
310	REGEN_DECLARED_USER	NULL	VARCHAR2(30)
	The REGEN DECLARED USER is the name of the individual who provided the regeneration declaration for the standards unit.		
320	REGEN_DECLARED_DATE	NULL	DATE
	The REGEN DECLARED DATE is the date of the regeneration declaration for the standards unit.		
330	REGEN_DECLARE_SUBMIT_DATE	NULL	DATE
	The REGEN DECLARE SUBMIT DATE is the date of the submission of the regeneration declaration date.		
340	FREE_GROW_EARLY_OFFSET_YRS	NULL	NUMBER(2,0)
	The FREE GROW EARLY OFFSET YRS is the minimum year for the reporting of the free growing forest cover survey for the standards unit.		
350	FREE_GROW_LATE_OFFSET_YRS	NULL	NUMBER(2,0)
	The FREE GROW LATE OFFSET YRS is the maximum year for the reporting of the free growing forest cover survey for the standards unit.		
360	FREE_GROW_DUE_EARLY_DATE	NULL	DATE
	The FREE GROW DUE EARLY DATE is the minimum date for the reporting of the free growing forest cover survey for the standards unit.		
370	FREE_GROW_DUE_LATE_DATE	NULL	DATE

Table: RSLT_STANDARDS_UNIT_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	The FREE GROW DUE LATE DATE is the maximum date for the reporting of the free growing forest cover survey for the standards unit.		
380	FREE_GROW_DECLARED_IND	NULL	VARCHAR2(1)
	The FREE GROW DECLARED IND is a system generated flag 'Y/N' which is set when a free growing declaration has been made for the standards unit.		
390	FREE_GROW_DECLARED_USER	NULL	VARCHAR2(30)
	The FREE GROW DECLARED USER is the name of the individual who provided the free growing declaration for the standards unit.		
400	FREE_GROW_DECLARED_DATE	NULL	DATE
	The FREE GROW DECLARE DATE is the date of the free growing declaration for the standards unit.		
410	FREE_GROW_DECLARE_SUBMIT_DATE	NULL	DATE
	The FREE GROW DECLARE SUBMIT DATE is the date of the submission of the free growing declaration date.		
411	STANDARDS_UNIT_TYPE	NULL	VARCHAR2(7)
	The STANDARDS UNIT TYPE describes the standards unit type characteristics: EVEN, UNEVEN, NONE and UNKOWN.		
420	I_MIN_STOCKING_STANDARD	NULL	NUMBER(5,0)
	I MIN STOCKING STANDARD - even-aged stocking standards - Minimum number of trees per hectare of preferred and acceptable species.		
430	I_MIN_PREF_STOCKING_STANDARD	NULL	NUMBER(5,0)
	I MIN PREF STOCKING STANDARD - even-aged stocking standard - Minimum number of trees per hectare of preferred species.		
440	I_TARGET_STOCKING	NULL	NUMBER(5,0)
	I TARGET STOCKING - even-aged stocking standards - Target number of trees per hectare of preferred and acceptable species		
450	I_RESIDUAL_BASAL_AREA	NULL	NUMBER(5,0)
	I RESIDUAL BASAL AREA - even-aged stocking standard. The basal area per hectare left standing after harvest		
460	I_MIN_HORIZONTAL_DISTANCE	NULL	NUMBER(3,1)
	I MIN HORIZONTAL DISTANCE - even-aged stocking standard - minimum horizontal distance between trees in metres.		
470	I_MIN_POST_SPACING	NULL	NUMBER(10,0)
	I MIN POST SPACING - even-aged stocking standard - Minimum density of well-spaced preferred and/or acceptable stems/ha to which the stand must be spaced to achieve free growing status.		
480	I_MAX_POST_SPACING	NULL	NUMBER(10,0)
	I MAX POST SPACING - even-aged stocking standard - Maximum density of well-spaced preferred and/or acceptable stems/ha to which the stand must be spaced to achieve free growing status.		
490	I_MAX_CONIFER	NULL	NUMBER(10,0)
	I MAX CONIFER - even-aged stocking standard - maximum allowable stand density of total countable conifers,m above which openings must be spaced down to a specified density of well-spaced preferred and/or acceptable stems, to achieve free growing status.		
500	I_HEIGHT_RELATIVE_TO_COMP	NULL	NUMBER(5,0)
	I HEIGHT RELATIVE TO COMP - even-aged stocking standard - Required minimum height of the tree above competing vegetation in a 1 metre radius, expressed as percentage or cm.		
510	I_TREE_SIZE_UNIT_CODE	NULL	VARCHAR2(3)
	I TREE SIZE UNIT CODE - the unit of measure related to the height relative to comp (above brush). Units in expressed as % or cm.		
520	I_PREFERRED_SPECIES1	NULL	VARCHAR2(8)
	I PREFERRED SPECIES1 - even-aged stocking standard - the preferred species that a healthy, well-spaced tree must attain in order to be considered free growing.		
530	I_PREFERRED_HEIGHT1	NULL	NUMBER(3,1)
	I PREFERRED HEIGHT1- even-aged stocking standard - the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
540	I_PREFERRED_SPECIES2	NULL	VARCHAR2(8)
	I PREFERRED SPECIES2 - even-aged stocking standard - the preferred species that a healthy, well-spaced tree must attain in order to be considered free growing.		
550	I_PREFERRED_HEIGHT2	NULL	NUMBER(3,1)

Table: RSLT_STANDARDS_UNIT_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	I PREFERRED HEIGHT2 - even-aged stocking standard - the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
560	I_PREFERRED_SPECIES3	NULL	VARCHAR2(8)
	I PREFERRED SPECIES3 - even-aged stocking standard - the preferred species that a healthy, well-spaced tree must attain in order to be considered free growing.		
570	I_PREFERRED_HEIGHT3	NULL	NUMBER(3,1)
	I PREFERRED HEIGHT3 - even-aged stocking standard - the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
580	I_PREFERRED_SPECIES4	NULL	VARCHAR2(8)
	I PREFERRED SPECIES4 - even-aged stocking standard - the preferred species that a healthy, well-spaced tree must attain in order to be considered free growing.		
590	I_PREFERRED_HEIGHT4	NULL	NUMBER(3,1)
	I PREFERRED HEIGHT4 - even-aged stocking standard - the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
600	I_PREFERRED_SPECIES5	NULL	VARCHAR2(8)
	I PREFERRED SPECIES5 - even-aged stocking standard - the preferred species that a healthy, well-spaced tree must attain in order to be considered free growing.		
610	I_PREFERRED_HEIGHT5	NULL	NUMBER(3,1)
	I PREFERRED HEIGHT5 - even-aged stocking standard - the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
620	I_MORE_PREF_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	I MORE PREF SPECIES EXIST IND - Even-aged stand with more than 5 preferred species than those listed.		
630	I_ACCEPTABLE_SPECIES1	NULL	VARCHAR2(8)
	I ACCEPTABLE SPECIES1 - even-aged stocking standard - the acceptable species that a healthy, well-spaced tree must attain in order to be considered free growing.		
640	I_ACCEPTABLE_HEIGHT1	NULL	NUMBER(3,1)
	I ACCEPTABLE HEIGHT1 - even-aged stocking standard - the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
650	I_ACCEPTABLE_SPECIES2	NULL	VARCHAR2(8)
	I ACCEPTABLE SPECIES2 - even-aged stocking standard - the acceptable species that a healthy, well-spaced tree must attain in order to be considered free growing.		
660	I_ACCEPTABLE_HEIGHT2	NULL	NUMBER(3,1)
	I ACCEPTABLE HEIGHT2 - even-aged stocking standard - the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
670	I_ACCEPTABLE_SPECIES3	NULL	VARCHAR2(8)
	I ACCEPTABLE SPECIES3 - even-aged stocking standard - the acceptable species that a healthy, well-spaced tree must attain in order to be considered free growing.		
680	I_ACCEPTABLE_HEIGHT3	NULL	NUMBER(3,1)
	I ACCEPTABLE HEIGHT3 - even-aged stocking standard -the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
690	I_ACCEPTABLE_SPECIES4	NULL	VARCHAR2(8)
	I ACCEPTABLE SPECIES4 - even-aged stocking standard - the acceptable species that a healthy, well-spaced tree must attain in order to be considered free growing.		
700	I_ACCEPTABLE_HEIGHT4	NULL	NUMBER(3,1)
	I ACCEPTABLE HEIGHT4 - even-aged stocking standard -the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
710	I_ACCEPTABLE_SPECIES5	NULL	VARCHAR2(8)
	I ACCEPTABLE SPECIES5 - even-aged stocking standard -the acceptable species that a healthy, well-spaced tree must attain in order to be considered free growing.		
720	I_ACCEPTABLE_HEIGHT5	NULL	NUMBER(3,1)
	I ACCEPTABLE HEIGHT5 - even-aged stocking standard - the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
730	I_MORE_ACC_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	I MORE ACC SPECIES EXIST IND - Even-aged stand with more than 5 acceptable species than those listed.		
740	I1_MIN_STOCKING_STANDARD	NULL	NUMBER(5,0)

Table: RSLT_STANDARDS_UNIT_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	I1 MIN STOCKING STANDARD - uneven-aged stocking standards Layer1- Mature - Minimum number of trees per hectare of preferred and acceptable species.		
750	I1_MIN_PREF_STOCKING_STANDARD	NULL	NUMBER(5,0)
	I1 MIN PREF STOCKING STANDARD - uneven-aged stocking standards Layer1- Mature - Target number of trees per hectare of preferred and acceptable species		
760	I1_TARGET_STOCKING	NULL	NUMBER(5,0)
	I1 TARGET STOCKING - uneven-aged stocking standards Layer 1-Mature - Target number of trees per hectare of preferred and acceptable species		
770	I1_RESIDUAL_BASAL_AREA	NULL	NUMBER(5,0)
	I1 RESIDUAL BASAL AREA - uneven-aged stocking standard Layer 1- Mature. The basal area per hectare left standing after harvest		
780	I1_MIN_HORIZONTAL_DISTANCE	NULL	NUMBER(3,1)
	I1 MIN HORIZONTAL DISTANCE - uneven-aged stocking standard Layer 1- Mature - minimum horizontal distance between trees in metres.		
790	I1_MIN_POST_SPACING	NULL	NUMBER(10,0)
	I1 MIN POST SPACING - uneven-aged stocking standard Layer 1- Mature - Minimum density of well-spaced preferred and/or acceptable stems/ha to which the stand must be spaced to achieve free growing status.		
800	I1_MAX_POST_SPACING	NULL	NUMBER(10,0)
	I1 MAX POST SPACING - uneven-aged stocking standard Layer 1- Mature - Maximum density of well-spaced preferred and/or acceptable stems/ha to which the stand must be spaced to achieve free growing status.		
810	I1_MAX_CONIFER	NULL	NUMBER(10,0)
	I1 MAX CONIFER - uneven-aged stocking standard Layer 1- Mature - maximum allowable stand density of total countable conifers,m above which openings must be spaced down to a specified density of well-spaced preferred and/or acceptable stems, to achieve free growing status.		
820	I1_HEIGHT_RELATIVE_TO_COMP	NULL	NUMBER(5,0)
	I1 HEIGHT RELATIVE TO COMP - uneven-aged stocking standard Layer 1- Mature - Required minimum height of the tree above competing vegetation in a 1 metre radius, expressed as percentage or cm.		
830	I1_TREE_SIZE_UNIT_CODE	NULL	VARCHAR2(3)
	I1 TREE SIZE UNIT CODE - even-aged stocking standard Layer 1- Mature - the unit of measure related to the height relative to comp (above brush). Units in expressed as % or cm.		
840	I1_PREFERRED_SPECIES1	NULL	VARCHAR2(8)
	I1 PREFERRED SPECIES1 - uneven-aged Layer 1- Mature stocking standards species1- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
850	I1_PREFERRED_HEIGHT1	NULL	NUMBER(3,1)
	I1 PREFERRED HEIGHT1 - uneven-aged Layer 1- Mature stocking standards species1- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
860	I1_PREFERRED_SPECIES2	NULL	VARCHAR2(8)
	I1 PREFERRED SPECIES2 - uneven-aged Layer 1- Mature stocking standards species2- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
870	I1_PREFERRED_HEIGHT2	NULL	NUMBER(3,1)
	I1 PREFERRED HEIGHT2 - uneven-aged Layer 1- Mature stocking standards species2- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
880	I1_PREFERRED_SPECIES3	NULL	VARCHAR2(8)
	I1 PREFERRED SPECIES3 - uneven-aged Layer 1- Mature stocking standards species3- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
890	I1_PREFERRED_HEIGHT3	NULL	NUMBER(3,1)
	I1 PREFERRED HEIGHT3 - uneven-aged Layer 1- Mature stocking standards species3- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
900	I1_PREFERRED_SPECIES4	NULL	VARCHAR2(8)
	I1 PREFERRED SPECIES4 - uneven-aged Layer 1- Mature stocking standards species4- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
910	I1_PREFERRED_HEIGHT4	NULL	NUMBER(3,1)
	I1 PREFERRED HEIGHT4 - uneven-aged Layer 1- Mature stocking standards species4- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
920	I1_PREFERRED_SPECIES5	NULL	VARCHAR2(8)

Table: RSLT_STANDARDS_UNIT_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	I1 PREFERRED SPECIES - uneven-aged Layer 1- Mature stocking standards species5- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
930	I1_PREFERRED_HEIGHT5	NULL	NUMBER(3,1)
	I1 PREFERRED HEIGHT5 - uneven-aged Layer 1- Mature stocking standards species5- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
940	I1_MORE_PREF_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	I1 MORE PREF SPECIES EXIST IND - uneven-aged stocking standard Layer 2- Pole. The basal area per hectare left standing after harvest		
950	I1_ACCEPTABLE_SPECIES1	NULL	VARCHAR2(8)
	I1 ACCEPTABLE SPECIES1 - uneven-aged Layer 1- Mature stocking standards species1- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
960	I1_ACCEPTABLE_HEIGHT1	NULL	NUMBER(3,1)
	I1 ACCEPTABLE HEIGHT1 - uneven-aged Layer 1- Mature stocking standards species1- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
970	I1_ACCEPTABLE_SPECIES2	NULL	VARCHAR2(8)
	I1 ACCEPTABLE SPECIES2 - uneven-aged Layer 1- Mature stocking standards species2- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
980	I1_ACCEPTABLE_HEIGHT2	NULL	NUMBER(3,1)
	I1 ACCEPTABLE HEIGHT2 - uneven-aged Layer 1- Mature stocking standards species2- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
990	I1_ACCEPTABLE_SPECIES3	NULL	VARCHAR2(8)
	I1 ACCEPTABLE SPECIES3 - uneven-aged Layer 1- Mature stocking standards species3- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1000	I1_ACCEPTABLE_HEIGHT3	NULL	NUMBER(3,1)
	I1 ACCEPTABLE HEIGHT3 - uneven-aged Layer 1- Mature stocking standards species3- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1010	I1_ACCEPTABLE_SPECIES4	NULL	VARCHAR2(8)
	I1 ACCEPTABLE SPECIES4 - uneven-aged Layer 1- Mature stocking standards species4- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1020	I1_ACCEPTABLE_HEIGHT4	NULL	NUMBER(3,1)
	I1 ACCEPTABLE HEIGHT4 - uneven-aged Layer 1- Mature stocking standards species4- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1030	I1_ACCEPTABLE_SPECIES5	NULL	VARCHAR2(8)
	I1 ACCEPTABLE SPECIES5 - uneven-aged Layer 1- Mature stocking standards species5- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1040	I1_ACCEPTABLE_HEIGHT5	NULL	NUMBER(3,1)
	I1 ACCEPTABLE HEIGHT5 - uneven-aged Layer 1- Mature stocking standards species5- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1050	I1_MORE_ACC_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	I1 MORE ACC SPECIES EXIST IND- uneven-aged Layer 1-Mature with more than 5 acceptable species than those listed.		
1060	I2_MIN_STOCKING_STANDARD	NULL	NUMBER(5,0)
	I2 MIN STOCKING STANDARD - uneven-aged stocking standards Layer2- Pole - Minimum number of trees per hectare of preferred and acceptable species.		
1070	I2_MIN_PREF_STOCKING_STANDARD	NULL	NUMBER(5,0)
	I2 MIN PREF STOCKING STANDARD - uneven-aged stocking standards Layer2- Pole - Target number of trees per hectare of preferred and acceptable species		
1080	I2_TARGET_STOCKING	NULL	NUMBER(5,0)
	I2 TARGET STOCKING - uneven-aged stocking standards Layer 2-Pole - Target number of trees per hectare of preferred and acceptable species		
1090	I2_RESIDUAL_BASAL_AREA	NULL	NUMBER(5,0)
	I2 RESIDUAL BASAL AREA - uneven-aged stocking standard Layer 2- Pole. The basal area per hectare left standing after harvest		
1100	I2_MIN_HORIZONTAL_DISTANCE	NULL	NUMBER(3,1)
	I2 MIN HORIZONTAL DISTANCE - uneven-aged stocking standard Layer 2- Pole - minimum horizontal distance between trees in metres.		
1110	I2_MIN_POST_SPACING	NULL	NUMBER(10,0)

Table: RSLT_STANDARDS_UNIT_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	I2 MIN POST SPACING - uneven-aged stocking standard Layer 2- Pole - Minimum density of well-spaced preferred and/or acceptable stems/ha to which the stand must be spaced to achieve free growing status.		
1120	I2_MAX_POST_SPACING	NULL	NUMBER(10,0)
	I2 MAX POST SPACING - uneven-aged stocking standard Layer 2- Pole - Maximum density of well-spaced preferred and/or acceptable stems/ha to which the stand must be spaced to achieve free growing status.		
1130	I2_MAX_CONIFER	NULL	NUMBER(10,0)
	I2 MAX CONIFER - uneven-aged stocking standard Layer 2- Pole - maximum allowable stand density of total countable conifers,m above which openings must be spaced down to a specified density of well-spaced preferred and/or acceptable stems, to achieve free growing status.		
1140	I2_HEIGHT_RELATIVE_TO_COMP	NULL	NUMBER(5,0)
	I2 HEIGHT RELATIVE TO COMP - uneven-aged stocking standard Layer 2- Pole - Required minimum height of the tree above competing vegetation in a 1 metre radius, expressed as percentage or cm.		
1150	I2_TREE_SIZE_UNIT_CODE	NULL	VARCHAR2(3)
	I2 TREE SIZE UNIT CODE - uneven-aged stocking standard Layer 2- Pole. The unit of measure related to the height relative to comp (above brush). Units in expressed as % or cm.		
1160	I2_PREFERRED_SPECIES1	NULL	VARCHAR2(8)
	I2 PREFERRED SPECIES1 - uneven-aged Layer 2- Pole stocking standards species1- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1170	I2_PREFERRED_HEIGHT1	NULL	NUMBER(3,1)
	I2 PREFERRED HEIGHT1 - uneven-aged Layer 2- Pole stocking standards species1- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1180	I2_PREFERRED_SPECIES2	NULL	VARCHAR2(8)
	I2 PREFERRED SPECIES2 - uneven-aged Layer 2- Pole stocking standards species2- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1190	I2_PREFERRED_HEIGHT2	NULL	NUMBER(3,1)
	I2 PREFERRED HEIGHT2 - uneven-aged Layer 2- Pole stocking standards species2- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1200	I2_PREFERRED_SPECIES3	NULL	VARCHAR2(8)
	I2 PREFERRED SPECIES3 - uneven-aged Layer 2- Pole stocking standards species3- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1210	I2_PREFERRED_HEIGHT3	NULL	NUMBER(3,1)
	I2 PREFERRED HEIGHT3 - uneven-aged Layer 2- Pole stocking standards species3- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1220	I2_PREFERRED_SPECIES4	NULL	VARCHAR2(8)
	I2 PREFERRED SPECIES4 - uneven-aged Layer 2- Pole stocking standards species4- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1230	I2_PREFERRED_HEIGHT4	NULL	NUMBER(3,1)
	I2 PREFERRED HEIGHT4 - uneven-aged Layer 2- Pole stocking standards species4- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1240	I2_PREFERRED_SPECIES5	NULL	VARCHAR2(8)
	I2 PREFERRED SPECIES5 - uneven-aged Layer 2- Pole stocking standards species5- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1250	I2_PREFERRED_HEIGHT5	NULL	NUMBER(3,1)
	I2 PREFERRED HEIGHT5 - uneven-aged Layer 2- Pole stocking standards species5- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1260	I2_MORE_PREF_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	I2 MORE PREF SPECIES EXIST IND - Uneven-aged stand - Layer 2-Pole with more than 5 preferred species than those listed.		
1270	I2_ACCEPTABLE_SPECIES1	NULL	VARCHAR2(8)
	I2 ACCEPTABLE HEIGHT1 - uneven-aged Layer 2- Pole stocking standards species1- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1280	I2_ACCEPTABLE_HEIGHT1	NULL	NUMBER(3,1)
	I2 ACCEPTABLE HEIGHT1 - uneven-aged Layer 2- Pole stocking standards species1- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1290	I2_ACCEPTABLE_SPECIES2	NULL	VARCHAR2(8)
	I2 ACCEPTABLE SPECIES2 - uneven-aged Layer 2- Pole stocking standards species2- the minimum		

Table: RSLT_STANDARDS_UNIT_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1300	I2_ACCEPTABLE_HEIGHT2	NULL	NUMBER(3,1)
	I2 ACCEPTABLE HEIGHT2 - uneven-aged Layer 2- Pole stocking standards species2- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1310	I2_ACCEPTABLE_SPECIES3	NULL	VARCHAR2(8)
	I2 ACCEPTABLE SPECIES3 - uneven-aged Layer 2- Pole stocking standards species3- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1320	I2_ACCEPTABLE_HEIGHT3	NULL	NUMBER(3,1)
	I2 ACCEPTABLE HEIGHT3 - uneven-aged Layer 2- Pole stocking standards species3- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1330	I2_ACCEPTABLE_SPECIES4	NULL	VARCHAR2(8)
	I2 ACCEPTABLE SPECIES4 - uneven-aged Layer 2- Pole stocking standards species4- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1340	I2_ACCEPTABLE_HEIGHT4	NULL	NUMBER(3,1)
	I2 ACCEPTABLE HEIGHT4 - uneven-aged Layer 2- Pole stocking standards species4- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1350	I2_ACCEPTABLE_SPECIES5	NULL	VARCHAR2(8)
	I2 ACCEPTABLE SPECIES5 - uneven-aged Layer 2- Pole stocking standards species5- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1360	I2_ACCEPTABLE_HEIGHT5	NULL	NUMBER(3,1)
	I2 ACCEPTABLE HEIGHT5 - uneven-aged Layer 2- Pole stocking standards species5- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1370	I2_MORE_ACC_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	I2 MORE ACC SPECIES EXIST IND - Uneven-aged stand - Layer 2-Pole with more than 5 acceptable species than those listed.		
1380	I3_MIN_STOCKING_STANDARD	NULL	NUMBER(5,0)
	I3 MIN STOCKING STANDARD - uneven-aged stocking standards Layer3- Sapling - Minimum number of trees per hectare of preferred and acceptable species.		
1390	I3_MIN_PREF_STOCKING_STANDARD	NULL	NUMBER(5,0)
	I3 MIN PREF STOCKING STANDARD - uneven-aged stocking standards Layer3- Sapling - Target number of trees per hectare of preferred and acceptable species		
1400	I3_TARGET_STOCKING	NULL	NUMBER(5,0)
	I3 TARGET STOCKING - uneven-aged stocking standards Layer 3-Sapling - Target number of trees per hectare of preferred and acceptable species		
1410	I3_RESIDUAL_BASAL_AREA	NULL	NUMBER(5,0)
	Residual Basal Area - uneven-aged stocking standard Layer 3- Sapling. The basal area per hectare left standing after harvest		
1420	I3_MIN_HORIZONTAL_DISTANCE	NULL	NUMBER(3,1)
	I3 MIN HORIZONTAL DISTANCE - uneven-aged stocking standard Layer 3- Sapling - minimum horizontal distance between trees in metres.		
1430	I3_MIN_POST_SPACING	NULL	NUMBER(10,0)
	I3 MIN POST SPACING - uneven-aged stocking standard Layer 3- Sapling - Minimum density of well-spaced preferred and/or acceptable stems/ha to which the stand must be spaced to achieve free growing status.		
1440	I3_MAX_POST_SPACING	NULL	NUMBER(10,0)
	I3 MAX POST SPACING - uneven-aged stocking standard Layer 3- Sapling - Maximum density of well-spaced preferred and/or acceptable stems/ha to which the stand must be spaced to achieve free growing status.		
1450	I3_MAX_CONIFER	NULL	NUMBER(10,0)
	I3 MAX CONIFER - uneven-aged stocking standard Layer 3- Sapling - maximum allowable stand density of total countable conifers,m above which openings must be spaced down to a specified density of well-spaced preferred and/or acceptable stems, to achieve free growing status.		
1460	I3_HEIGHT_RELATIVE_TO_COMP	NULL	NUMBER(5,0)
	I3 HEIGHT RELATIVE TO COMP - uneven-aged stocking standard Layer 3- Sapling - Required minimum height of the tree above competing vegetation in a 1 metre radius, expressed as percentage or cm.		
1470	I3_TREE_SIZE_UNIT_CODE	NULL	VARCHAR2(3)
	I3 TREE SIZE UNIT CODE - uneven-aged stocking standard Layer 3- Sapling. The unit of measure		

Table: RSLT_STANDARDS_UNIT_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	related to the height relative to comp (above brush). Units in expressed as % or cm.		
1480	I3_PREFERRED_SPECIES1	NULL	VARCHAR2(8)
	I3 PREFERRED SPECIES1- uneven-aged Layer3- Sapling stocking standards species1- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1490	I3_PREFERRED_HEIGHT1	NULL	NUMBER(3,1)
	I3 PREFERRED HEIGHT1 - uneven-aged Layer3- Sapling stocking standards species1- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1500	I3_PREFERRED_SPECIES2	NULL	VARCHAR2(8)
	I3 PREFERRED SPECIES2 - uneven-aged Layer3- Sapling stocking standards species2- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1510	I3_PREFERRED_HEIGHT2	NULL	NUMBER(3,1)
	I3 PREFERRED HEIGHT2 - uneven-aged Layer3- Sapling stocking standards species2- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1520	I3_PREFERRED_SPECIES3	NULL	VARCHAR2(8)
	I3 PREFERRED SPECIES3 - uneven-aged Layer3- Sapling stocking standards species3- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1530	I3_PREFERRED_HEIGHT3	NULL	NUMBER(3,1)
	I3 PREFERRED HEIGHT3 - uneven-aged Layer3- Sapling stocking standards species3- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1540	I3_PREFERRED_SPECIES4	NULL	VARCHAR2(8)
	I3 PREFERRED SPECIES4 - uneven-aged Layer3- Sapling stocking standards species4- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1550	I3_PREFERRED_HEIGHT4	NULL	NUMBER(3,1)
	I3 PREFERRED HEIGHT4 - uneven-aged Layer3- Sapling stocking standards species4- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1560	I3_PREFERRED_SPECIES5	NULL	VARCHAR2(8)
	I3 PREFERRED SPECIES5 - uneven-aged Layer3- Sapling stocking standards species5- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1570	I3_PREFERRED_HEIGHT5	NULL	NUMBER(3,1)
	I3 PREFERRED HEIGHT5 - uneven-aged Layer3- Sapling stocking standards species5- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1580	I3_MORE_PREF_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	I3 MORE PREF SPECIES EXIST IND - Uneven-aged stand - Layer 3-Sapling with more than 5 preferred species than those listed.		
1590	I3_ACCEPTABLE_SPECIES1	NULL	VARCHAR2(8)
	I3 ACCEPTABLE SPECIES1 - uneven-aged Layer3- Sapling stocking standards species1- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1600	I3_ACCEPTABLE_HEIGHT1	NULL	NUMBER(3,1)
	I3 ACCEPTABLE HEIGHT1 - uneven-aged Layer3- Sapling stocking standards species1- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1610	I3_ACCEPTABLE_SPECIES2	NULL	VARCHAR2(8)
	I3 ACCEPTABLE SPECIES2 - uneven-aged Layer3- Sapling stocking standards species2- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1620	I3_ACCEPTABLE_HEIGHT2	NULL	NUMBER(3,1)
	I3 ACCEPTABLE HEIGHT2 - uneven-aged Layer3- Sapling stocking standards species2- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1630	I3_ACCEPTABLE_SPECIES3	NULL	VARCHAR2(8)
	I3 ACCEPTABLE SPECIE3 - uneven-aged Layer3- Sapling stocking standards species3- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1640	I3_ACCEPTABLE_HEIGHT3	NULL	NUMBER(3,1)
	I3 ACCEPTABLE HEIGHT3 - uneven-aged Layer3- Sapling stocking standards species3- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1650	I3_ACCEPTABLE_SPECIES4	NULL	VARCHAR2(8)
	I3 ACCEPTABLE SPECIES4 - uneven-aged Layer3- Sapling stocking standards species4- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1660	I3_ACCEPTABLE_HEIGHT4	NULL	NUMBER(3,1)
	I3 ACCEPTABLE HEIGHT4 - uneven-aged Layer3- Sapling stocking standards species4- the minimum		

Table: RSLT_STANDARDS_UNIT_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1670	I3_ACCEPTABLE_SPECIES5	NULL	VARCHAR2(8)
	I3 ACCEPTABLE SPECIES5 - uneven-aged Layer3- Sapling stocking standards species5- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1680	I3_ACCEPTABLE_HEIGHT5	NULL	NUMBER(3,1)
	I3 ACCEPTABLE HEIGHT5 - uneven-aged Layer3- Sapling stocking standards species5- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1690	I3_MORE_ACC_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	I3 MORE ACC SPECIES EXIST IND - Uneven-aged stand - Layer 3-Sapling with more than 5 acceptable species than those listed.		
1700	I4_MIN_STOCKING_STANDARD	NULL	NUMBER(5,0)
	I4 MIN STOCKING STANDARD - uneven-aged stocking standards Layer4- Regen - Minimum number of trees per hectare of preferred and acceptable species.		
1710	I4_MIN_PREF_STOCKING_STANDARD	NULL	NUMBER(5,0)
	I4 MIN PREF STOCKING STANDARD - uneven-aged stocking standards Layer4- Regen - Target number of trees per hectare of preferred and acceptable species		
1720	I4_TARGET_STOCKING	NULL	NUMBER(5,0)
	I4 TARGET STOCKING - uneven-aged stocking standards Layer 4-Regen - Target number of trees per hectare of preferred and acceptable species		
1730	I4_RESIDUAL_BASAL_AREA	NULL	NUMBER(5,0)
	I4 RESIDUAL BASAL AREA - uneven-aged stocking standard Layer 4- Regen. The basal area per hectare left standing after harvest		
1740	I4_MIN_HORIZONTAL_DISTANCE	NULL	NUMBER(3,1)
	I4 MIN HORIZONTAL DISTANCE - uneven-aged stocking standard Layer 4- Regen - minimum horizontal distance between trees in metres.		
1750	I4_MIN_POST_SPACING	NULL	NUMBER(10,0)
	I4 MIN POST SPACING - uneven-aged stocking standard Layer 4- Regen - Minimum density of well-spaced preferred and/or acceptable stems/ha to which the stand must be spaced to achieve free growing status.		
1760	I4_MAX_POST_SPACING	NULL	NUMBER(10,0)
	I4 MAX POST SPACING - uneven-aged stocking standard Layer 4- Regen - Maximum density of well-spaced preferred and/or acceptable stems/ha to which the stand must be spaced to achieve free growing status.		
1770	I4_MAX_CONIFER	NULL	NUMBER(10,0)
	I4 MAX CONIFER- uneven-aged stocking standard Layer 4- Regen - maximum allowable stand density of total countable conifers,m above which openings must be spaced down to a specified density of well-spaced preferred and/or acceptable stems, to achieve free growing status.		
1780	I4_HEIGHT_RELATIVE_TO_COMP	NULL	NUMBER(5,0)
	I4 HEIGHT RELATIVE TO COMP - uneven-aged stocking standard Layer 4- Regen - Required minimum height of the tree above competing vegetation in a 1 metre radius, expressed as percentage or cm.		
1790	I4_TREE_SIZE_UNIT_CODE	NULL	VARCHAR2(3)
	I4 TREE SIZE UNIT CODE -uneven-aged stocking standard Layer 4- Regen. The unit of measure related to the height relative to comp (above brush). Units in expressed as % or cm.		
1800	I4_PREFERRED_SPECIES1	NULL	VARCHAR2(8)
	I4 PREFERRED SPECIES1 - uneven-aged Layer4- Regen stocking standards species1- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1810	I4_PREFERRED_HEIGHT1	NULL	NUMBER(3,1)
	I4 PREFERRED HEIGHT1- uneven-aged Layer4- Regen stocking standards species1- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1820	I4_PREFERRED_SPECIES2	NULL	VARCHAR2(8)
	I4 PREFERRED SPECIES2 - uneven-aged Layer4- Regen stocking standards species2- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1830	I4_PREFERRED_HEIGHT2	NULL	NUMBER(3,1)
	I4 PREFERRED HEIGHT2 - uneven-aged Layer4- Regen stocking standards species2- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1840	I4_PREFERRED_SPECIES3	NULL	VARCHAR2(8)
	I4 PREFERRED SPECIES3 - uneven-aged Layer4- Regen stocking standards species3- the minimum		

Table: RSLT_STANDARDS_UNIT_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
	species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1850	I4_PREFERRED_HEIGHT3	NULL	NUMBER(3,1)
	I4 PREFERRED HEIGHT3 - for uneven-aged Layer4- Regen stocking standards species3- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1860	I4_PREFERRED_SPECIES4	NULL	VARCHAR2(8)
	I4 PREFERRED SPECIES4 - uneven-aged Layer4- Regen stocking standards species4- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1870	I4_PREFERRED_HEIGHT4	NULL	NUMBER(3,1)
	I4 PREFERRED HEIGHT4 - uneven-aged Layer4- Regen stocking standards species4- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1880	I4_PREFERRED_SPECIES5	NULL	VARCHAR2(8)
	I4 PREFERRED SPECIES5 - uneven-aged Layer4- Regen stocking standards species5- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1890	I4_PREFERRED_HEIGHT5	NULL	NUMBER(3,1)
	I4 PREFERRED HEIGHT5 - uneven-aged Layer4- Regen stocking standards species5- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1900	I4_MORE_PREF_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	I4 MORE PREF SPECIES EXIST IND - Uneven-aged stand - Layer 4-Regen with more than 5 preferred species than those listed.		
1910	I4_ACCEPTABLE_SPECIES1	NULL	VARCHAR2(8)
	I4 ACCEPTABLE SPECIES1 - uneven-aged Layer4- Regen stocking standards species1- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1920	I4_ACCEPTABLE_HEIGHT1	NULL	NUMBER(3,1)
	I4 ACCEPTABLE HEIGHT1 - uneven-aged Layer4- Regen stocking standards species1- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1930	I4_ACCEPTABLE_SPECIES2	NULL	VARCHAR2(8)
	I4 ACCEPTABLE SPECIES2 - uneven-aged Layer4- Regen stocking standards species2- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1940	I4_ACCEPTABLE_HEIGHT2	NULL	NUMBER(3,1)
	I4 ACCEPTABLE HEIGHT2 - uneven-aged Layer4- Regen stocking standards species2- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1950	I4_ACCEPTABLE_SPECIES3	NULL	VARCHAR2(8)
	I4 ACCEPTABLE SPECIES3 - uneven-aged Layer4- Regen stocking standards species3- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1960	I4_ACCEPTABLE_HEIGHT3	NULL	NUMBER(3,1)
	I4 ACCEPTABLE HEIGHT3 - uneven-aged Layer4- Regen stocking standards species3- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1970	I4_ACCEPTABLE_SPECIES4	NULL	VARCHAR2(8)
	I4 ACCEPTABLE SPECIES4 - uneven-aged Layer4- Regen stocking standards species4- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
1980	I4_ACCEPTABLE_HEIGHT4	NULL	NUMBER(3,1)
	I4 ACCEPTABLE HEIGHT4 - uneven-aged Layer4- Regen stocking standards species4- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
1990	I4_ACCEPTABLE_SPECIES5	NULL	VARCHAR2(8)
	I4 ACCEPTABLE SPECIES5 - uneven-aged Layer4- Regen stocking standards species5- the minimum species that a healthy, well-spaced tree must attain in order to be considered free growing.		
2000	I4_ACCEPTABLE_HEIGHT5	NULL	NUMBER(3,1)
	I4 ACCEPTABLE HEIGHT5 - uneven-aged Layer4- Regen stocking standards species5- the minimum height that a healthy, well-spaced tree must attain in order to be considered free growing.		
2010	I4_MORE_ACC_SPECIES_EXIST_IND	NULL	VARCHAR2(1)
	I4 MORE ACC SPECIES EXIST IND - Uneven-aged stand - Layer 4-Regen with more than 5 acceptable species than those listed.		
2020	GEOMETRY_EXIST_IND	NULL	VARCHAR2(1)
	The GEOMETRY EXIST IND indicates if there is geometry for the opening. A value of 'Y' indicates there is geometry. A value of 'N' indicates there is no geometry.		
2029	GEOMETRY	NULL	
	The GEOMETRY is the standards unit geographical representation.		

Table: RSLT_STANDARDS_UNIT_SVW (cont'd)

Columns:

Seq.	Column	Nulls?	Type
2030	FEATURE_AREA	NULL	NUMBER(11,4)
	The FEATURE AREA is the area of the standards unit in square meters.		
2040	FEATURE_PERIMETER	NULL	NUMBER(11,4)
	The FEATURE PERIMETER is the perimeter of the standards unit in meters.		
2050	CAPTURE_METHOD_CODE	NULL	VARCHAR2(30)
	The CAPTURE METHOD CODE is a code defining the capture method. (e.g. digitize).		
2060	DATA_SOURCE_CODE	NULL	VARCHAR2(10)
	The DATA SOURCE CODE is a code defining the source of the spatial feature (e.g. GPS, TRIM).		
2070	FEATURE_CLASS_SKEY	NULL	NUMBER(10,0)
	The FEATURE CLASS SKEY is the unique key assigned to a Feature Class by the Ministry of Forests.		
2080	OBSERVATION_DATE	NULL	DATE
	The OBSERVATION DATE is the geometry collection date.		
2090	DATA_QUALITY_COMMENT	NULL	VARCHAR(255)
	The DATA QUALITY COMMENT is a comment indicating the Geometry accuracy.		
2100	SSU_WHO_CREATED	NOT NULL	VARCHAR2(30)
	The SSU WHO CREATED is the USERID of the individual who created the standards unit record.		
2110	SSU_WHEN_CREATED	NOT NULL	DATE
	The SSU WHEN CREATED is the date and time when the standards unit record was created.		
2120	SSU_WHO_UPDATED	NOT NULL	VARCHAR2(30)
	The SSU WHO UPDATED is the USERID of the individual who last updated the standards unit record.		
2130	SSU_WHEN_UPDATED	NOT NULL	DATE
	The SSU WHEN UPDATED is the date and time when the standards unit record was last updated.		
2140	OBJECTID	NOT NULL	NUMBER(10,0)
	The OBJECTID is a system generated value uniquely identifying the opening. Used by SDE.		